
common-ovf-tool Documentation

Release 1.7.4

the COT project developers

September 21, 2016

1	Introduction	1
1.1	Examples	1
2	Installing COT	3
2.1	System requirements	3
2.2	Installing COT using <code>pip</code>	3
2.3	Installing COT from source	4
2.4	Installing helper programs	4
3	Using COT	7
3.1	Getting CLI help	7
3.2	Verifying and installing helper programs with <code>cot install-helpers</code>	8
3.3	Inspecting OVF contents with <code>cot info</code>	10
3.4	Updating product information with <code>cot edit-product</code>	10
3.5	Adding disks to an OVF with <code>cot add-disk</code>	11
3.6	Packaging additional files into an OVF with <code>cot add-file</code>	12
3.7	Removing files from an OVF with <code>cot remove-file</code>	12
3.8	Customizing hardware profiles with <code>cot edit-hardware</code>	13
3.9	Customizing OVF environment settings with <code>cot edit-properties</code>	15
3.10	Embedding bootstrap configuration with <code>cot inject-config</code>	17
3.11	Deploying an OVF to create a VM with <code>cot deploy</code>	17
3.12	Creating a VM on VMware vCenter/vSphere with <code>cot deploy esxi</code>	18
4	Change Log	21
4.1	1.7.4 - 2016-09-21	21
4.2	1.7.3 - 2016-09-06	21
4.3	1.7.2 - 2016-08-17	21
4.4	1.7.1 - 2016-08-12	21
4.5	1.7.0 - 2016-08-05	22
4.6	1.6.1 - 2016-07-07	22
4.7	1.6.0 - 2016-06-30	22
4.8	1.5.2 - 2016-06-17	23
4.9	1.5.1 - 2016-06-07	23
4.10	1.5.0 - 2016-06-06	23
4.11	1.4.2 - 2016-05-11	24
4.12	1.4.1 - 2015-09-02	24
4.13	1.4.0 - 2015-09-01	24
4.14	1.3.3 - 2015-07-02	25

4.15	1.3.2 - 2015-04-09	25
4.16	1.3.1 - 2015-04-09	25
4.17	1.3.0 - 2015-03-27	25
4.18	1.2.4 - 2015-03-06	26
4.19	1.2.3 - 2015-02-19	26
4.20	1.2.2 - 2015-02-19	26
4.21	1.2.1 - 2015-02-03	26
4.22	1.2.0 - 2015-01-16	27
4.23	1.1.6 - 2015-01-05	27
4.24	1.1.5 - 2014-11-25	27
4.25	1.1.4 - 2014-11-12	27
4.26	1.1.3 - 2014-10-01	28
4.27	1.1.2 - 2014-09-24	28
4.28	1.1.1 - 2014-08-19	28
4.29	1.1.0 - 2014-07-29	28
4.30	1.0.0 - 2014-06-27	29
5	Contributing to COT	31
5.1	Follow coding guidelines	31
5.2	Add automated unit tests	32
5.3	Update documentation	33
5.4	Add yourself as a contributor	33
5.5	Open a pull request	33
6	Credits	35
7	COT package reference	37
7.1	Virtual machine definition modules	37
7.2	Command modules	48
7.3	Helper library modules	64
7.4	User interface modules	73
7.5	Sub-packages	78
8	Indices and tables	107
	Python Module Index	109

Introduction

COT (the Common OVF Tool) is a tool for editing [Open Virtualization Format](#) (.ovf, .ova) virtual appliances, with a focus on virtualized network appliances such as the [Cisco CSR 1000V](#) and [Cisco IOS XRv](#) platforms.

COT's capabilities include:

- Add a disk or other file to an OVF/OVA
- Edit OVF hardware information (CPUs, RAM, NICs, configuration profiles, etc.)
- Edit product description information in an OVF/OVA
- Edit OVF environment properties
- Display a descriptive summary of the contents of an OVA or OVF package
- Embed a bootstrap configuration text file into an OVF/OVA.
- Remove files and disks from an OVF or OVA package
- Deploy an OVF/OVA to an ESXi (VMware vSphere or vCenter) server to provision a new virtual machine (VM).

1.1 Examples

Displaying a summary of OVA contents:

```
> cot info --brief csr1000v-universalk9.03.17.01.S.156-1.S1-std.ova
-----
csr1000v-universalk9.03.17.01.S.156-1.S1-std.ova
COT detected platform type: Cisco CSR1000V
-----
Product:  Cisco CSR 1000V Cloud Services Router
Vendor:    Cisco Systems, Inc.
Version:   03.17.01.S.156-1.S1-std

Files and Disks:                File Size  Capacity Device
-----
  csr1000v_hddisk.vmdk          71.5 KiB    8 GiB hddisk @ SCSI 0:0
  bdeo.sh                       52.42 KiB
  README-OVF.txt                 8.534 KiB
  README-BDEO.txt                6.748 KiB
  cot.tgz                       116.8 KiB
  csr1000v-universalk9.03.17.... 425 MiB          cdrom @ IDE 1:0

Hardware Variants:
```

```

System types:          vmx-08 vmx-09 vmx-10 vmx-11
                      Cisco:Internal:VMcloud-01
SCSI device types:    virtio lsilogic
Ethernet device types: VMXNET3 virtio

Configuration Profiles: CPUs      Memory NICs Serials Disks/Capacity
-----
1CPU-4GB (default)    1        4 GiB   3        2 1 /      8 GiB
2CPU-4GB              2        4 GiB   3        2 1 /      8 GiB
4CPU-4GB              4        4 GiB   3        2 1 /      8 GiB
4CPU-8GB              4        8 GiB   3        2 1 /      8 GiB

Networks:
GigabitEthernet1     "Data network 1"
GigabitEthernet2     "Data network 2"
GigabitEthernet3     "Data network 3"

Environment:
Transport types: iso

Properties:
<config-version>          "1.0"
Router Name               ""
Login Username            ""
Login Password            ""
Management Interface      "GigabitEthernet1"
Management VLAN           ""
Management Interface IPv4 Address/Mask ""
Management IPv4 Gateway   ""
Management IPv4 Network   ""
PNSC IPv4 Address         ""
PNSC Agent Local Port     ""
PNSC Shared Secret Key    ""
Remote Management IPv4 Address (optional, deprecated) ""
Enable SCP Server         "false"
Enable SSH Login and Disable Telnet Login "false"
Enable Password           ""
Domain Name               ""
License boot level        "ax"
Console                   ""
Resource template         "default"
Intercloud Mode           ""
Intercloud Mode Management Key ""
Intercloud Control Port   ""
Intercloud Tunnel Port    ""
Intercloud Tunnel Header Size "148"
Intercloud Tunnel Interface IPv4 Address ""
Intercloud Tunnel Interface Gateway IPv4 Address ""

```

Adding a custom hardware configuration profile to an OVA:

```
> cot edit-hardware csr1000v.ova --output csr1000v_custom.ova \
  --profile 1CPU-4GB --cpus 1 --memory 4GB
```

Customizing OVF environment properties:

```
> cot edit-properties csr1000v.ova --output csr1000v_custom.ova \
  --properties mgmt-ipv4-addr=10.1.1.100/24 \
  mgmt-ipv4-gateway=10.1.1.1
```

Installing COT

- *System requirements*
- *Installing COT using pip*
 - *Installing optional features*
- *Installing COT from source*
 - *Downloading COT*
 - *Install the COT libraries and script*
- *Installing helper programs*

2.1 System requirements

- COT requires either Python 2.7 or Python 3.3 or later.
- COT is tested to work under Mac OS X and Ubuntu Linux and similar distros.
- COT now has limited support for CentOS and Python 2.6 as well.

2.2 Installing COT using pip

Since COT is written in Python, it can be installed like any other Python package using the `pip` tool. For most users this is the recommended installation method.

```
sudo pip install cot
```

If you have already installed COT and wish to update to the latest available version:

```
sudo pip install --upgrade cot
```

2.2.1 Installing optional features

COT has a number of optional Python package dependencies that enable optional features. If you want to use these features, you can instruct `pip` to install them as part of the COT installation process, or you can install them separately after the fact.

- Tab-completion of COT CLI parameters in `bash`, enabled with the `argcomplete` package.

```
sudo pip install cot[tab-completion]
```

or

```
sudo pip install argcomplete
```

Note: After installing `argcomplete` by either method, you must configure your `bash` environment to enable it. Refer to the `argcomplete` documentation for the required steps.

2.3 Installing COT from source

If you wish to install bleeding-edge unreleased code or make code contributions of your own, you can install COT from source as described below.

2.3.1 Downloading COT

You can download COT via Git or using HTTP.

```
git clone git://github.com/glennmatthews/cot
cd cot
```

or

```
wget -O cot.tgz https://github.com/glennmatthews/cot/archive/master.tar.gz
tar xzf cot.tgz
cd cot-master
```

or

```
curl -o cot.tgz https://github.com/glennmatthews/cot/archive/master.tar.gz
tar xzf cot.tgz
cd cot-master
```

2.3.2 Install the COT libraries and script

```
sudo python setup.py install
```

2.4 Installing helper programs

Certain COT features require helper programs - you can install these as part of the COT installation process, or they can be installed as-needed by COT:

- COT uses `qemu-img` as a helper program for various operations involving the creation, inspection, and modification of hard disk image files packaged in an OVF.
- The `cot add-disk` command requires either `qemu-img` (version 2.1 or later) or `vmdktool` as a helper program when adding hard disks to an OVF.
- The `cot inject-config` command requires `mkisofs` (or its fork `genisoimage`) and/or `xorriso` to create ISO (CD-ROM) images for platforms that use ISOs to package the configuration.

- Similarly, for platforms using hard disks for bootstrap configuration, `cot inject-config` requires [fatdisk](#) to format hard disk images.
- The `cot deploy ... esxi` command requires [ovftool](#) to communicate with an ESXi server. If `ovftool` is installed, COT's automated unit tests will also make use of `ovftool` to perform additional verification that OVFs and OVAs created by COT align with VMware's expectations for these file types.

COT can attempt to install these tools using the appropriate package manager for your platform (i.e., [MacPorts](#) for Mac OS X, and either `apt-get` or `yum` for Linux).

Warning: Unfortunately, VMware requires a site login to download [ovftool](#), so if you need this tool, you will have to install it yourself. COT cannot install it for you at present.

To let COT attempt to pre-install all of the above helpers, you can optionally run:

```
cot install-helpers
```

See [here](#) for more details.

If you skip this step, then when you are running COT, and it encounters the need for a helper that has not been installed, COT will prompt you to allow it to install the helper in question.

Using COT

3.1 Getting CLI help

3.1.1 Synopsis

```
cot --help
cot --version
cot help <command>
cot <command> --help
cot <options> <command> <command-options>
```

3.1.2 Description

Common OVF Tool (COT), version 1.7.4+0.g1eb2bf5.dirty

A tool for editing Open Virtualization Format (.ovf, .ova) virtual appliances, with a focus on virtualized network appliances such as the Cisco CSR 1000V and Cisco IOS XRv platforms.

You can always get detailed help for COT by running `cot --help`, `cot <command> --help`, or `cot help <command>`.

3.1.3 Options

-h, --help	show this help message and exit
-V, --version	show program's version number and exit
-f, --force	Perform requested actions without prompting for confirmation
-q, --quiet	Quiet output and logging (warnings and errors only)
-v, --verbose	Verbose output and logging
-d, --debug	Debug (most verbose) output and logging

Commands

add-disk Add a disk image to an OVF package and map it as a disk in the guest environment

add-file Add a file to an OVF package

deploy Create a new VM on the target hypervisor from the given OVF or OVA

edit-hardware Edit virtual machine hardware properties of an OVF

edit-product Edit product info in an OVF

edit-properties Edit or create environment properties of an OVF

help Print help for a command

info Generate a description of an OVF package

inject-config Inject a configuration file into an OVF package

install-helpers Install/verify COT manual pages and any third- party helper programs that COT may require

remove-file Remove a file from an OVF package

3.2 Verifying and installing helper programs with `cot install-helpers`

3.2.1 Synopsis

```
cot install-helpers --help
cot <opts> install-helpers --verify-only
cot <opts> install-helpers [--ignore-errors]
```

3.2.2 Description

Install or verify the installation of COT manual pages and various required third-party helper programs for COT.

- `qemu-img` (<http://www.qemu.org/>)
- `mkisofs` (<http://cdrecord.org/>)
- `ovftool` (<https://www.vmware.com/support/developer/ovf/>)
- `fatdisk` (<http://github.com/goblinhack/fatdisk>)
- `vmdktool` (<http://www.freshports.org/sysutils/vmdktool/>)

3.2.3 Options

- | | |
|----------------------------|--|
| -h, --help | show this help message and exit |
| --verify-only | Only verify helpers – do not attempt to install any missing helpers. |
| -i, --ignore-errors | Do not fail even if helper installation fails. |

3.2.4 Examples

Verify whether COT can find all expected helper programs

```
> cot install-helpers --verify-only
Results:
-----
COT manpages: present in /usr/share/man/man1/
fatdisk:      present at /opt/local/bin/fatdisk
mkisofs:      present at /opt/local/bin/mkisofs
ovftool:      present at /usr/local/bin/ovftool
qemu-img:     present at /opt/local/bin/qemu-img
vmdktool:     NOT FOUND
```

Have COT attempt to install missing helpers for you. Note that most helpers require administrator / sudo privileges to install. If any installation fails, COT will exit with an error, unless you pass `--ignore-errors`.

```
> cot install-helpers
  INFO: Installing 'fatdisk'...
  INFO: Compiling 'fatdisk'
  INFO: Calling './RUNME'...
(...)
  INFO: ...done
  INFO: Compilation complete, installing to /usr/local/bin
  INFO: Successfully installed 'fatdisk'
  INFO: Calling 'fatdisk --version' and capturing its output...
  INFO: ...done
  INFO: Installing 'vmdktool'...
  INFO: vmdktool requires 'zlib'... installing 'zlib'
  INFO: Calling 'dpkg -s zlib1g-dev' and capturing its output...
  INFO: ...done
  INFO: Compiling 'vmdktool'
  INFO: Calling 'make CFLAGS="-D_GNU_SOURCE -g -O -pipe"'...
(...)
  INFO: ...done
  INFO: Compilation complete, installing to /usr/local
  INFO: Calling 'make install'...
install -s vmdktool /usr/local/bin/
install vmdktool.8 /usr/local/man/man8/
  INFO: ...done
  INFO: Successfully installed 'vmdktool'
  INFO: Calling 'vmdktool -V' and capturing its output...
  INFO: ...done
  INFO: Copying cot-add-disk.1 to /usr/share/man/man1/cot-add-disk.1
(...)
  INFO: Copying cot.1 to /usr/share/man/man1/cot.1
Results:
-----
COT manpages: successfully installed to /usr/share/man
fatdisk:      successfully installed to /usr/local/bin/fatdisk
mkisofs:      present at /usr/bin/mkisofs
ovftool:      INSTALLATION FAILED: No support for automated
               installation of ovftool, as VMware requires a site
               login to download it. See
               https://www.vmware.com/support/developer/ovf/
qemu-img:     present at /usr/bin/qemu-img
vmdktool:     successfully installed to /usr/local/bin/vmdktool

Unable to install some helpers
```

Warning: Unfortunately, VMware requires a site login to download `ovftool`, so if you need this tool, you will have to install it yourself. COT cannot install it for you at present.

3.3 Inspecting OVF contents with `cot info`

3.3.1 Synopsis

```
cot info --help
cot info [-b | -v] PACKAGE [PACKAGE ...]
```

3.3.2 Description

Show a summary of the contents of the given OVF(s) and/or OVA(s).

3.3.3 Options

PACKAGE [PACKAGE ...] OVF descriptor(s) and/or OVA file(s) to describe

- h, --help** show this help message and exit
- b, --brief** Brief output (shorter)
- v, --verbose** Verbose output (longer)

3.4 Updating product information with `cot edit-product`

3.4.1 Synopsis

```
cot edit-product --help
cot <opts> edit-product PACKAGE [-o OUTPUT] [-c PRODUCT_CLASS]
                                [-p PRODUCT] [-n VENDOR] [-v SHORT_VERSION]
                                [-V FULL_VERSION] [-u PRODUCT_URL ]
                                [-r VENDOR_URL] [-l APPLICATION_URL]
```

3.4.2 Description

Edit product information attributes of the given OVF or OVA

3.4.3 Options

PACKAGE OVF descriptor or OVA file to edit

- h, --help** show this help message and exit
- o OUTPUT, --output OUTPUT** Name/path of new OVF/OVA package to create instead of updating the existing OVF
- c PRODUCT_CLASS, --product-class PRODUCT_CLASS** Product class, such as “com.cisco.csr1000v”
- p PRODUCT, --product PRODUCT** Product name string, such as “Cisco IOS-XE”

- n VENDOR, --vendor VENDOR** Vendor string, such as “Cisco Systems, Inc.”
- v SHORT_VERSION, --version SHORT_VERSION** Software short version string, such as “15.3(4)S” or “5.2.0.01I”
- V FULL_VERSION, --full-version FULL_VERSION** Software long version string, such as “Cisco IOS-XE Software, Version 15.3(4)S”
- u PRODUCT_URL, --product-url PRODUCT_URL** Product URL, such as “<http://www.cisco.com/go/iosxrv>”
- r VENDOR_URL, --vendor-url VENDOR_URL** Vendor URL, such as “<http://www.cisco.com>”
- l APPLICATION_URL, --application-url APPLICATION_URL** Application URL, such as “<https://router1:530/>”

3.5 Adding disks to an OVF with `cot add-disk`

3.5.1 Synopsis

```
cot add-disk --help
cot <opts> add-disk DISK_IMAGE PACKAGE [-o OUTPUT] [-f FILE_ID]
                        [-t {harddisk,cdrom}] [-c {ide,scsi}]
                        [-s SUBTYPE] [-a ADDRESS] [-d DESCRIPTION]
                        [-n DISKNAME]
```

3.5.2 Description

Add or replace a disk image in the specified OVF or OVA. If the specified disk image, controller/address, file-id, and/or instance match an existing entry in the OVF, will replace the existing disk with the provided file (prompting for confirmation if `-force` was not set); otherwise, will create a new disk entry.

3.5.3 Options

DISK_IMAGE Disk image file to add to the package

PACKAGE OVF descriptor or OVA file to edit

General options

- h, --help** Show this help message and exit
- o OUTPUT, --output OUTPUT** Name/path of new OVF/OVA package to create instead of updating the existing OVF

Disk-related options

- f FILE_ID, --file-id FILE_ID** Disk image file ID string within the OVF package (default: use disk image filename)
- t <harddisk,cdrom>, --type <harddisk,cdrom>** Disk type (default: files ending in `.vmdk/.raw/.qcow2/.img` will use `harddisk` and files ending in `.iso` will use `cdrom`)

Controller-related options

- c <ide,scsi>, --controller <ide,scsi>** Disk controller type (default: determined by disk type and platform)
- a ADDRESS, --address ADDRESS** Address of the disk, such as “1:0”. Requires that `--controller` be explicitly set. (default: use first unused address on the controller)
- s SUBTYPE, --subtype SUBTYPE** Disk controller subtype such as “virtio” or “lsilogic”.

Descriptive options

- d DESCRIPTION, --description DESCRIPTION** Description of this disk (optional)
- n DISKNAME, --name DISKNAME** Name of this disk (default: “Hard disk #” or “CD-ROM #” as appropriate)

3.6 Packaging additional files into an OVF with `cot add-file`

3.6.1 Synopsis

```
cot add-file --help
cot <opts> add-file FILE PACKAGE [-o OUTPUT] [-f FILE_ID]
```

3.6.2 Description

Add or replace a file in the given OVF. If the specified file and/or file-id match existing package contents, will replace it (prompting for confirmation if `--force` was not set); otherwise, will create a new file entry.

3.6.3 Options

FILE File to add to the package

PACKAGE Package, OVF descriptor or OVA file to edit

- h, --help** show this help message and exit
- o OUTPUT, --output OUTPUT** Name/path of new VM package to create instead of updating the existing package
- f FILE_ID, --file-id FILE_ID** File ID string within the package (default: same as filename)

3.7 Removing files from an OVF with `cot remove-file`

3.7.1 Synopsis

```
cot remove-file --help
cot <opts> remove-file [-f FILE_PATH] [-i FILE_ID] PACKAGE
                        [-o OUTPUT]
```


3.7.2 Description

Remove a file from the given OVF. Will prompt for confirmation unless `--force` is set.

3.7.3 Options

PACKAGE Package, OVF descriptor or OVA file to edit

General options

- h, --help** Show this help message and exit
- o OUTPUT, --output OUTPUT** Name/path of new OVF/OVA package to create instead of updating the existing OVF

File selection options

- f FILE_PATH, --file-path FILE_PATH** File name or path within the package
- i FILE_ID, --file-id FILE_ID** File ID string within the package

3.8 Customizing hardware profiles with `cot edit-hardware`

3.8.1 Synopsis

```
cot edit-hardware --help
cot <opts> edit-hardware PACKAGE [-o OUTPUT] -v TYPE [TYPE2 ...]
cot <opts> edit-hardware PACKAGE [-o OUTPUT]
                                [-p PROFILE [PROFILE2 ...]
                                [--delete-all-other-profiles]] [-c CPUS]
                                [-m MEMORY] [-n NICS]
                                [--nic-types TYPE [TYPE2 ...]]
                                [-N NETWORK [NETWORK2 ...]]
                                [-M MAC1 [MAC2 ...]]
                                [--nic-names NAME1 [NAME2 ...]]
                                [-s SERIAL_PORTS] [-S URI1 [URI2 ...]]
                                [--scsi-subtypes TYPE [TYPE2 ...]]
                                [--ide-subtypes TYPE [TYPE2 ...]]
```

3.8.2 Description

Edit hardware properties of the specified OVF or OVA

3.8.3 Options

PACKAGE OVF descriptor or OVA file to edit

General options

- h, --help** Show this help message and exit
- o OUTPUT, --output OUTPUT** Name/path of new OVF/OVA package to create instead of updating the existing OVF
- v <TYPE...>, --virtual-system-type <TYPE...>** Change virtual system type(s) supported by this OVF/OVA package.
- p <PROFILE...>, --profiles <PROFILE...>** Make hardware changes only under the given configuration profile(s). (default: changes apply to all profiles)
- delete-all-other-profiles** Delete all configuration profiles other than those specified with the `--profiles` option

Computational hardware options

- c CPUS, --cpus CPUS** Set the number of CPUs.
- m MEMORY, --memory MEMORY** Set the amount of RAM. (Examples: “4096M”, “4 GiB”)

Network interface options

- n NICS, --nics NICS** Set the number of NICs.
- nic-types <TYPE...>** Set the hardware type(s) for all NICs. (default: do not change existing NICs, and new NICs added will match the existing type(s).)
- nic-names <NAME1...>** Specify a list of one or more NIC names or patterns to apply to NIC devices. See Notes.
- N <NETWORK...>, --nic-networks <NETWORK...>** Specify a series of one or more network names or patterns to map NICs to. See Notes.
- network-descriptions <NAME1...>** Specify a list of one or more network descriptions or patterns to apply to the networks. See Notes.
- M <MAC1...>, --mac-addresses-list <MAC1...>** Specify a list of MAC addresses for the NICs. If N MACs are specified, the first (N-1) NICs will receive the first (N-1) MACs, and all remaining NICs will receive the Nth MAC

Serial port options

- s SERIAL_PORTS, --serial-ports SERIAL_PORTS** Set the number of serial ports.
- S <URI1...>, --serial-connectivity <URI1...>** Specify a series of connectivity strings (URIs such as “telnet://localhost:9101”) to map serial ports to. If fewer URIs than serial ports are specified, the remaining ports will be unmapped.

Disk and disk controller options

- scsi-subtypes <TYPE...>** Set resource subtype(s) (such as “lsilogic” or “virtio”) for all SCSI controllers. If an empty string is provided, any existing subtype will be removed.
- ide-subtypes <TYPE...>** Set resource subtype(s) (such as “virtio”) for all IDE controllers. If an empty string is provided, any existing subtype will be removed.

3.8.4 Notes

The `--nic-names`, `--nic-networks`, and `--network-descriptions` options support the use of a wildcard value to automatically generate a series of consecutively numbered strings. The syntax for the wildcard option is `{` followed by a number to start incrementing from, followed by `}`. See examples below.

3.8.5 Examples

Create a new profile named “1CPU-8GB” with 1 CPU and 8 gigabytes of RAM

```
cot edit-hardware csr1000v.ova --output csr1000v_custom.ova \
  --profile 1CPU-4GB --cpus 1 --memory 8GB
```

Wildcard example - without caring about how many NICs are defined in the input OVA, rename all of the NICs in the output OVA as ‘Ethernet0/10’, ‘Ethernet0/11’, ‘Ethernet0/12’, etc., and map them to networks ‘Ethernet0_10’, ‘Ethernet0_11’, ‘Ethernet0_12’, etc., which are described as ‘Data network 1’, ‘Data network 2’, etc.

```
cot edit-hardware input.ova -o output.ova \
  --nic-names "Ethernet0/{10}" \
  --nic-networks "Ethernet0_{10}" \
  --network-descriptions "Data network {1}"
```

Combination of fixed and wildcarded names - rename the NICs in the output OVA as ‘mgmt’, ‘eth0’, ‘eth1’, ‘eth2’...

```
cot edit-hardware input.ova -o output.ova --nic-names "mgmt" \
  "eth{0}"
```

3.9 Customizing OVF environment settings with cot edit-properties

3.9.1 Synopsis

```
cot edit-properties --help
cot <opts> edit-properties PACKAGE
                                [-p KEY1=VALUE1 [-p KEY2=VALUE2 ...]]
                                [-l LABEL1 [-l LABEL2 ...]]
                                [-d DESC1 [-d DESC2 ...]] [-c CONFIG_FILE]
                                [-u [USER_CONFIGURABLE]]
                                [-t TRANSPORT [TRANSPORT2 ...]]
                                [-o OUTPUT]
cot <opts> edit-properties PACKAGE [-u [USER_CONFIGURABLE]]
                                [-o OUTPUT]
```

3.9.2 Description

Configure environment properties of the given OVF or OVA. The user may specify keys and values as command-line arguments or may provide a config-file to read from. If neither `--config-file`, `--properties`, nor `--transport` are given, the program will run interactively.

3.9.3 Options

PACKAGE OVF descriptor or OVA file to edit

General options

- h, --help** Show this help message and exit
- o OUTPUT, --output OUTPUT** Name/path of new OVF/OVA package to create instead of updating the existing OVF

Property setting options

- u <USER_CONFIGURABLE>, --user-configurable <USER_CONFIGURABLE>** Update the 'userConfigurable' flag on all edited properties to True or the given value
- c CONFIG_FILE, --config-file CONFIG_FILE** Read configuration CLI from this text file and generate generic properties for each line of CLI
- p <KEY1[=VALUE1][+TYPE1]...>, --properties <KEY1[=VALUE1][+TYPE1]...>** Update or create the given property keys. A '=' delimits the optional value to set this key to. A '+' delimits the optional type to enforce for this key. This argument may be repeated as needed to specify multiple properties to edit.
- l <LABEL1...>, --labels <LABEL1...>** Set the label(s) for the property(s) being edited. If this option is specified, the number of properties and the number of labels *must* be equal.
- d <DESC1...>, --descriptions <DESC1...>** Set the description(s) for the property(s) being edited. If this option is specified, the number of properties and the number of descriptions *must* be equal.
- t <TRANSPORT...>, --transports <TRANSPORT...>** Set the transport method(s) for properties. Known values are 'iso', 'vmware', and 'ibm', or an arbitrary URI may be specified.

3.9.4 Examples

Add configuration from a text file and mark the resulting properties as non-user-configurable.

```
cot edit-properties input.ovf -c config.txt -u=0
```

Add/update two properties, one a string with no default value and the other a boolean defaulting to true, and mark both properties as user-configurable.

```
cot edit-properties input.ovf -p string-property+string \  
-p bool-property=true+boolean --user-configurable
```

Update the label and description of two existing properties

```
cot edit-properties input.ovf -p hostname -l "Hostname" \  
-d "Hostname of this device" -p enable-ssh -l "Enable \  
remote SSH access" -d "Enable sshd and disable telnetd"
```

3.10 Embedding bootstrap configuration with `cot inject-config`

3.10.1 Synopsis

```
cot inject-config --help
cot <opts> inject-config PACKAGE -c CONFIG_FILE [-o OUTPUT]
cot <opts> inject-config PACKAGE -s SECONDARY_CONFIG_FILE [-o OUTPUT]
cot <opts> inject-config PACKAGE -c CONFIG_FILE
                                -s SECONDARY_CONFIG_FILE [-o OUTPUT]
```

3.10.2 Description

Add one or more “bootstrap” configuration file(s) to the given OVF or OVA.

3.10.3 Options

PACKAGE Package, OVF descriptor or OVA file to edit

- h, --help** show this help message and exit
- o OUTPUT, --output OUTPUT** Name/path of new VM package to create instead of updating the existing package
- c CONFIG_FILE, --config-file CONFIG_FILE** Primary configuration text file to embed
- s SECONDARY_CONFIG_FILE, --secondary-config-file SECONDARY_CONFIG_FILE** Secondary configuration text file to embed (currently only supported in IOS XRv for admin config)

3.11 Deploying an OVF to create a VM with `cot deploy`

3.11.1 Synopsis

```
cot deploy --help
cot <opts> deploy PACKAGE esxi ...
```

3.11.2 Description

Deploy an OVF or OVA to create a virtual machine on a specified server.

3.11.3 Options

PACKAGE OVF descriptor or OVA file

- h, --help** show this help message and exit

Hypervisors

esxi Deploy to ESXi, vSphere, or vCenter

3.12 Creating a VM on VMware vCenter/vSphere with `cot deploy esxi`

3.12.1 Synopsis

```
cot deploy PACKAGE esxi --help
cot <opts> deploy PACKAGE esxi LOCATOR [-u USERNAME] [-p PASSWORD]
                                     [-c CONFIGURATION] [-n VM_NAME] [-P]
                                     [-N OVF1=HOST1 [-N OVF2=HOST2 ...]]
                                     [-S KIND1:VAL1[,OPTS1]
                                     [-S KIND2:VAL2[,OPTS2] ...]]
                                     [-d DATASTORE] [-o=OVFTOOL_ARGS]
```

3.12.2 Description

Deploy OVF/OVA to ESXi/vCenter/vSphere hypervisor

3.12.3 Options

LOCATOR vSphere target locator. Examples: “192.0.2.100” (deploy directly to ESXi server), “192.0.2.101/mydatacenter/host/192.0.2.100” (deploy via vCenter server)

- h, --help** show this help message and exit
- u USERNAME, --username USERNAME** Server login username
- p PASSWORD, --password PASSWORD** Server login password
- c CONFIGURATION, --configuration CONFIGURATION** Use the specified configuration profile defined in the OVF. If unspecified and the OVF has multiple profiles, the user will be prompted or the default configuration will be used.
- n VM_NAME, --vm-name VM_NAME** Name to use for the VM (if applicable) and any files created. If unspecified, the name of the OVF will be used.
- P, --power-on** Power on the created VM to begin booting immediately.
- N <OVF_NET1=HOST_NET1...>, --network-map <OVF_NET1=HOST_NET1...>** Map networks named in the OVF to networks (bridges, vSwitches, etc.) in the hypervisor environment. This argument may be repeated as needed to specify multiple mappings.
- S <K1:V1[,O1]...>, --serial-connection <K1:V1[,O1]...>** Set connectivity for a serial port defined in the OVF. This argument may be repeated to specify more port connections. Each entry should be structured as ‘kind:value’ or ‘kind:value,options’.
- d DATASTORE, --datastore DATASTORE** ESXi datastore to use for the new VM
- o OVFTOOL_ARGS, --ovftool-args OVFTOOL_ARGS** Quoted string describing additional CLI parameters to pass through to “ovftool”. Examples: -o=”-foo”, -ovftool-args=”-foo -bar”

3.12.4 Examples

Deploy to vSphere/ESXi server 192.0.2.100 with credentials admin/admin, creating a VM named 'test_vm' from foo.ova.

```
cot deploy foo.ova esxi 192.0.2.100 -u admin -p admin \  
-n test_vm
```

Deploy to vSphere/ESXi server 192.0.2.100, with username admin (prompting the user to input a password at runtime), creating a VM based on profile '1CPU-2.5GB' in foo.ova, and creating the serial port as a telnet server listening on port 10022 of the host

```
cot deploy foo.ova esxi 192.0.2.100 -u admin -c 1CPU-2.5GB \  
-S telnet://:10022,server
```

Deploy to vSphere server 192.0.2.1 which belongs to datacenter 'mydc' on vCenter server 192.0.2.100, and map the two NIC networks to vSwitches. Note that in this case -u specifies the vCenter login username.

```
cot deploy foo.ova esxi "192.0.2.100/mydc/host/192.0.2.1" \  
-u administrator -N "GigabitEthernet1=VM Network" \  
-N "GigabitEthernet2=myvswitch"
```

Deploy with passthrough arguments to ovftool.

```
cot deploy foo.ova esxi 192.0.2.100 -u admin -p password \  
--ovftool-args="--overwrite --acceptAllEulas"
```

Change Log

All notable changes to the COT project will be documented in this file. This project adheres to [Semantic Versioning](#).

4.1 1.7.4 - 2016-09-21

Newer versions of Sphinx have dropped support for Python 2.6 and 3.3, so I have updated COT's installation requirements to use older Sphinx versions under these Python versions.

4.2 1.7.3 - 2016-09-06

Added

- When adding NICs to an OVF, if no `-nic-networks` are specified, `cot edit-hardware` will now try to infer sequential naming of the Network elements and if successful, offer to create additional Networks as appropriate. (#18)

4.3 1.7.2 - 2016-08-17

Fixed

- Issue #52 - `OVFItemDataError` raised when adding NICs to CSR1000V OVA, or more generally when cloning an `OVFItem` whose `ElementName` references its `Connection`.

4.4 1.7.1 - 2016-08-12

Fixed

- `cot deploy ... --serial-connection` will create additional serial ports beyond those defined in the OVF, if requested. Previously it would ask the user for confirmation but not actually do anything about it. (#51)

4.5 1.7.0 - 2016-08-05

Added

- Support for Python 3.5
- Enhancements to `cot edit-properties` (#50):
 - Added `--user-configurable` option to set whether created/updated properties are marked as user-configurable in the OVF.
 - Added `--labels` and `--descriptions` options to set/update the labels and descriptions associated with properties.
 - It's now valid to set no default value for a property by omitting the `=value`, as in `-p property-with-no-value`, as well as the existing `-p property-with-empty-value=` syntax to set an empty string as the value.
 - Users can now optionally specify the property type to enforce for each property by using the delimiter `+type`, as in `-p key=1+boolean`.

Changed

- Switched from statement coverage to branch coverage for better test analysis.
- Moved from [Coveralls](#) to [Codecov](#) for test coverage tracking, since Coveralls does not support branch coverage reporting.

Fixed

- When `cot edit-hardware` is used to create new NICs in an OVF that previously had none, and the user does not specify any corresponding Network entries, automatically create a 'VM Network' entry, because all NICs must be mapped to Networks for a valid OVF descriptor.

4.6 1.6.1 - 2016-07-07

Fixed

- `ValueMismatchError` exceptions are properly caught by the CLI wrapper so as to result in a graceful exit rather than a stack trace.
- `cot remove-file` now errors if the user specifies both `file-id` and `file-path`, one of which matches a file in the OVF, but the other does not match this or any other file.
- Better handling of exceptions and usage of `sudo` when installing helpers.
- Manual pages are now correctly included in the distribution. Oops!

4.7 1.6.0 - 2016-06-30

Added

- `cot edit-product --product-class` option, to set or change the product class identifier (such as `com.cisco.csr1000v`).
- Enabled additional code quality validation with [Pylint](#), [pep8-naming](#), and [mccabe](#) (#49).

Changed

- Lots of refactoring to reduce code complexity as measured by [Pylint](#) and [mccabe](#).

Fixed

- COT now recognizes `AllocationUnits` values like megabytes.
- COT no longer ignores the `AllocationUnits` value given for RAM.
- `COT.ovf.byte_string()` now properly uses binary units (KiB rather than kB, etc.)

4.8 1.5.2 - 2016-06-17

Changed

- Development requirement changes: The package [pep8](#) has been renamed to [pycodestyle](#), and [pep257](#) has been renamed to [pydocstyle](#). Updated configuration and documentation to reflect these changes. Also, [flake8-pep257](#) does not presently handle these changes, so replaced it as a dependency with the more up-to-date [flake8-docstrings](#) package.

4.9 1.5.1 - 2016-06-07

Added

- `cot edit-hardware --network-descriptions` option, to specify the descriptive string(s) associated with each network definition.

Fixed

- [#48](#) - NIC type not set when adding NICs to an OVF that had none before.
- When updating NIC network mapping, COT now also updates any Description that references the network mapping.

4.10 1.5.0 - 2016-06-06

Added

- [#47](#) - Added `cot remove-file` subcommand.
- [#43](#) - add `cot edit-properties --transport` option to set environment transport type(s) - iso, VMWare Tools, etc.
 - `cot info` now has a new “Environment” section that displays the transport type
- [#45](#) - support for multiple values for `--nic-types`, `--ide-subtypes`, and `--scsi-subtypes` in `cot edit-hardware`.
- COT now recognizes the Cisco IOS XRv 9000 platform identifier `com.cisco.ios-xrv9000`.
- [#21](#) - subcommand aliases (Python 3.x only):
 - `cot edit-product` aliases: `cot set-product`, `cot set-version`
 - `cot edit-properties` aliases: `cot set-properties`, `cot edit-environment`, `cot set-environment`
 - `cot info` alias: `cot describe`

- `cot inject-config alias: cot add-bootstrap`
- `cot remove-file alias: cot delete-file`

- Support for tab-completion of CLI parameters using [argcomplete](#).

Changed

- `cot edit-hardware` options `--nic-types`, `--ide-subtypes`, and `--scsi-subtypes` are now validated and canonicalized by COT, meaning that:
 - `cot edit-hardware --nic-type virtio-net-pci` is now a valid command and will correctly create an OVF with `ResourceSubType virtio` (not `virtio-net-pci`)
 - `cot edit-hardware --ide-subtype foobar` will now fail with an error
- `cot info` is now more self-consistent in how it displays property keys. They are now always wrapped in `< >`, whereas previously this was only sometimes the case.
- `cot info --verbose` now displays file and disk ID strings under the “Files and Disks” section.

4.11 1.4.2 - 2016-05-11

Added

- COT now supports `xorriso` as another alternative to `mkisofs` and `genisoimage`

Fixed

- [#42](#) - `cot deploy esxi` error handling behavior needed to be updated for [requests](#) release 2.8.
- [#44](#) - test case failure seen when running [pyVmomi](#) 6.0.0.2016.4.

Changed

- Installation document now recommends installation via [pip](#) rather than installing from source.
- [#40](#) - Now uses faster Docker-based infrastructure from [Travis CI](#) for CI builds/tests.

4.12 1.4.1 - 2015-09-02

Fixed

- [#41](#) - symlinks were not dereferenced when writing out to OVA.

4.13 1.4.0 - 2015-09-01

Added

- [#24](#) - `cot deploy esxi` now creates serial ports after deployment using [pyVmomi](#) library.
 - Serial port connectivity must be specified either via entries in the OVF (which can be defined using `cot edit-hardware ... -S`) or at deployment time using the new `-S / --serial-connection` parameter to `cot deploy`.
 - The syntax for serial port connectivity definition is based on that of QEMU's `--serial` CLI option.
 - Currently only “telnet”, “tcp”, and “device” connection types are supported.

- [#38](#) - `cot edit-product` can now set product and vendor information.
- `flake8` validation now includes [pep257](#) to validate docstring compliance to [PEP 257](#) as well.
- Added changelog file.
- Added `COT.file_reference` submodule in support of [#39](#).

Changed

- Split ESXi-specific logic out of `COT.deploy` module and into new `COT.deploy_esxi` module.
- UT for `COT.deploy_esxi` now requires `mock` (standard library in Python 3.x, install via `pip` on Python 2.x).

Fixed

- [#39](#) - avoid unnecessary file copies to save time and disk space.

4.14 1.3.3 - 2015-07-02

Fixed

- [#10](#) - When changing network mapping, delete no longer needed networks
- [#31](#) - Added `--delete-all-other-profiles` option to `cot edit-hardware`
- [#32](#) - `cot edit-hardware` network names can now use wildcards
- [#34](#) - `cot add-disk` can now be used to replace a CD-ROM drive with a hard disk, or vice versa.

4.15 1.3.2 - 2015-04-09

Fixed

- Adapt to changes to the Travis-CI testing environment.

4.16 1.3.1 - 2015-04-09

Fixed

- [#30](#) - `cot install-helpers` can now install `fatdisk` and `vmtool` under Python 3.

4.17 1.3.0 - 2015-03-27

Added

- Installation of helper programs is now provided by a `cot install-helpers` subcommand rather than a separate script.
- COT now has man pages (`man cot`, `man cot-edit-hardware`, etc.) The man pages are also installed by `cot install-helpers`.
- Improved documentation of the CLI on [readthedocs.org](#) as well.

Changed

- Refactored `COT.helper_tools` module into `COT.helpers` subpackage. This package has an API (`COT.helpers.api`) for the rest of COT to access it; the helper-specific logic (`qemu-img`, `fatdisk`, etc.) is split into individual helper modules that are abstracted away by the API.
- Similarly, logic from `COT.tests.helper_tools` has been refactored and enhanced under `COT.helpers.tests`.
- Renamed all test code files from “foo.py” to “test_foo.py” to facilitate test case discovery.
- CLI help strings are dynamically rendered to ReST when docs are built, providing cleaner output for both readthedocs.org and the manpages.

Removed

- COT no longer supports Python 3.2.
- `cot_unittest` is no more - use `tox` or `unit2 discover` to run tests.
- As noted above, the installation script `check_and_install_helpers.py` no longer exists - this functionality is now provided by the `COT.install_helpers` module.

4.18 1.2.4 - 2015-03-06

Fixed

- [#29](#) - `cot edit-properties` interactive mode was broken in v1.2.2

4.19 1.2.3 - 2015-02-19

Fixed

- Some documentation fixes for <http://cot.readthedocs.org>

4.20 1.2.2 - 2015-02-19

Added

- Documentation built with Sphinx and available at <http://cot.readthedocs.org>

Changed

- CLI adapts more intelligently to terminal width (fixes [#28](#))
- Submodules now use Python properties instead of `get_value/set_value` methods.

4.21 1.2.1 - 2015-02-03

Added

- Now [PEP 8](#) compliant - passes validation by [flake8](#) code analysis.
- Very preliminary support for OVF 2.x format
- Now uses `tox` for easier test execution and `coverage.py` for code coverage analysis.
- Code coverage reporting with [Coveralls](#).

Changed

- Now uses `colorlog` instead of `coloredlogs` for CLI log colorization, as this fits better with COT's logging model.
- Greatly improved unit test structure and code coverage, including tests for logging.

4.22 1.2.0 - 2015-01-16

Added

- Greatly improved logging ([#26](#)). COT now defaults to logging level INFO, which provides relatively brief status updates to the user. You can also run with `--quiet` to suppress INFO messages and only log WARNING and ERROR messages, `--verbose` to see VERBOSE messages as well, or `--debug` if you want to really get into the guts of what COT is doing.
- Now integrated with [Travis CI](#) for automated builds and UT under all supported Python versions. This should greatly improve the stability of COT under less-common Python versions. ([#12](#))

Changed

- The CLI for `cot deploy` has been revised somewhat based on user feedback.
- A lot of restructuring of the underlying code to make things more modular and easier to test in isolation.

Fixed

- Various bugfixes for issues specific to Python 2.6 and 3.x - these environments should now be fully working again.

4.23 1.1.6 - 2015-01-05

Added

- Added THANKS file recognizing various non-code contributions to COT.

Fixed

- Bug fixes for `cot inject-config` and `cot deploy`, including issues [#19](#) and [#20](#) and a warning to users about serial ports and ESXi (issue eventually to be addressed by fixing [#24](#)).
- More graceful handling of Ctrl-C interrupt while COT is running.

4.24 1.1.5 - 2014-11-25

Fixed

- Fixed issue [#17](#) (`cot edit-hardware` adding NICs makes an OVA that vCenter regards as invalid)
- Removed several spurious WARNING messages

4.25 1.1.4 - 2014-11-12

Added

- COT can at least be installed and run under CentOS/Python2.6 now, although the automated unit tests will complain about the different XML output that 2.6 produces.

Changed

- Vastly improved installation workflow under Linuxes supporting `apt-get` or `yum` - included helper script can automatically install all helper programs except `ovftool`. Fixes #9.

Fixed

- Improved `cot deploy` handling of config profiles - fixed #5 and #15

4.26 1.1.3 - 2014-10-01

Added

- `cot edit-hardware` added `--nic-names` option for assigning names to each NIC
- `cot info` now displays NIC names.

Fixed

- Improved installation documentation
- Some improvements to IOS XRv OVA support

4.27 1.1.2 - 2014-09-24

Added

- Take advantage of QEMU 2.1 finally supporting the `streamOptimized` VMDK sub-format.
- Can now create new hardware items without an existing item of the same type (issue #4)

Changed

- Clearer documentation and logging messages (issue #8 and others)
- Now uses `versioneer` for automatic version numbering.

Fixed

- Fixed several Python 3 compatibility issues (issue #7 and others)

4.28 1.1.1 - 2014-08-19

Fixed

- Minor bug fixes to `cot deploy esxi`.

4.29 1.1.0 - 2014-07-29

Added

- `cot deploy esxi` subcommand by Kevin Keim (@kakeim), which uses `ovftool` to deploy an OVA to an ESXi vCenter server.

Changed

- Removed dependencies on `md5` / `md5sum` / `shasum` / `sha1sum` in favor of Python's `hashlib` module.
- Nicer formatting of `cot info` output

Fixed

- Miscellaneous fixes and code cleanup.

4.30 1.0.0 - 2014-06-27

Initial public release.

Contributing to COT

Please do contribute! We only have a few simple requirements for diffs and pull requests.

- *Follow coding guidelines*
- *Add automated unit tests*
- *Update documentation*
- *Add yourself as a contributor*
- *Open a pull request*

5.1 Follow coding guidelines

5.1.1 Logging level usage

ERROR Something is wrong (such as a violation of the OVF specification) but COT was able to attempt to recover. If recovery is not possible, you should raise an `Error` of appropriate type instead of logging an **ERROR** message.

WARNING Something unexpected or risky happened that the user needs a heads-up about. This includes cases where the software had to make an uncertain choice on its own due to lack of information from the user.

INFO Important status updates about normal operation of the software. As this is the lowest logging level enabled by default, you should keep the logs generated at this level relatively brief but meaningful.

VERBOSE Detailed information of interest to an advanced or inquisitive user.

DEBUG Highly detailed information only useful to a developer familiar with the code.

5.1.2 Coding style

We try to keep COT's code base compliant with Python coding standards including [PEP 8](#) and [PEP 257](#). We use the [flake8](#) and [Pylint](#) tools and their extension packages to verify this as part of our test automation. To run coding style analysis independently of the other test automation, you can run `tox -e flake8,pylint`, or you can install these tools and run them directly:

```
cot/$ sudo pip install --upgrade flake8
cot/$ sudo pip install --upgrade pydocstyle
cot/$ sudo pip install --upgrade flake8-docstrings
```

```
cot/$ sudo pip install --upgrade pep8-naming
cot/$ sudo pip install --upgrade mccabe
cot/$ flake8
./COT/ovf/item.py:229:1: C901 'OVFItem.value_replace_wildcards' is too complex (11)
./COT/ovf/item.py:603:1: C901 'OVFItem.generate_items' is too complex (11)
./COT/ovf/ovf.py:461:1: C901 'OVF.validate_hardware' is too complex (14)
```

```
cot/$ sudo pip install --upgrade pylint
cot/$ pylint COT
***** Module COT.ovf.item
E:331,24: Instance of 'list' has no 'split' member (no-member)
R:334,16: Redefinition of value type from list to tuple (redefined-variable-type)
R:603, 4: Too many branches (13/12) (too-many-branches)
***** Module COT.ovf.ovf
C: 1, 0: Too many lines in module (2646/2600) (too-many-lines)
R:177, 0: Too many public methods (76/74) (too-many-public-methods)
```

Fix any errors and warnings these tools report, and run again until no errors are reported.

5.2 Add automated unit tests

Whether adding new functionality or fixing a bug, **please** add appropriate unit test case(s) under `COT/tests/`, `COT/helpers/tests/`, or `COT/ovf/tests` (as appropriate) to cover your changes. Your changes **must** pass all existing and new automated test cases before your code will be accepted.

You can run the COT automated tests under a single Python version by running `python ./setup.py test`.

For full testing under all supported versions as well as verifying code coverage for your tests, you should install `tox` (pip install tox) and `coverage` (pip install coverage) then run `tox` from the COT directory:

```
cot/$ tox
...
py26 runtests: commands[0] | coverage run --append setup.py test --quiet
...
py27 runtests: commands[0] | coverage run --append setup.py test --quiet
...
py33 runtests: commands[0] | coverage run --append setup.py test --quiet
...
py34 runtests: commands[0] | coverage run --append setup.py test --quiet
...
pypy runtests: commands[0] | coverage run --append setup.py test --quiet
...
flake8 runtests: commands[0] | flake8 --verbose
...
pylint runtests: commands[0] | pylint COT
...
docs runtests: commands[0] | sphinx-build -W -b html -d ...
...
stats runtests: commands[0] | coverage combine
stats runtests: commands[1] | coverage report -i
Name                               Stmts  Miss  Cover
-----
COT/__init__.py                     5      0   100%
COT/add_disk.py                    166      1    99%
COT/add_file.py                     45      0   100%
COT/cli.py                         252     15    94%
COT/data_validation.py              88      0   100%
```

```

COT/deploy.py                148      4    97%
COT/deploy_esxi.py           201     28    86%
COT/edit_hardware.py          273      2    99%
...
COT/vm_description.py         168      4    98%
COT/vm_factory.py              26      0   100%
COT/xml_file.py               120      0   100%
-----
TOTAL                        4692    136    97%
stats runtests: commands[2] | coverage html -i
_____ summary _____
  setup: commands succeeded
  py26: commands succeeded
  py27: commands succeeded
  py33: commands succeeded
  py34: commands succeeded
  pypy: commands succeeded
  flake8: commands succeeded
  pylint: commands succeeded
  docs: commands succeeded
  stats: commands succeeded
  congratulations :)

```

After running `tox` you can check the code coverage details by opening `htmlcov/index.html` in a web browser.

5.3 Update documentation

If you add or change any COT CLI or APIs, or add or remove any external dependencies, please update the relevant documentation.

5.4 Add yourself as a contributor

If you haven't contributed to COT previously, be sure to add yourself as a contributor in the `COPYRIGHT.txt` file.

5.5 Open a pull request

COT follows Vincent Driessen's [A successful Git branching model](#). As such, please submit feature enhancement and non-critical bugfix requests to merge into the `develop` branch rather than `master`.

Credits

We would like to thank:

- For evangelization, user feedback and bug reports:
 - Arun Arunkumar
 - Mark Coverdill
 - Myles Dear
 - Jeff Loughridge
 - Jonathan Muslow
 - Rick Ogg
 - David Rosenfeld
 - Rafal Skorka
 - Perumal Venkatesh
- For initial design review and comments:
 - Andy Dalton
 - Jusheng Feng
 - Doug Gordon
 - Lina Long
 - Neil McGill
 - Vinod Pandarinathan
 - Rich Wellum
- For providing managerial support for the development and release of COT as open source:
 - Ray Romney
 - Sanjeev Tondale
 - Taskin Ucpinar
- Rich Wellum, for creating “Build, Deploy, Execute OVA” (`bdeo.sh`), the precursor to COT.
- Neil McGill, for creating and maintaining `fatdisk`
- Brian Somers, for creating and maintaining `vmdktool`

COT package reference

The below documents describe in depth the code structure and APIs of COT. These are not generally of interest to the end users of the COT script, but are provided for reference of developers wishing to integrate the COT package directly into their code. Package implementing the Common OVF Tool.

7.1 Virtual machine definition modules

<i>COT.vm_description</i>	Abstract superclass for reading, editing, and writing VMs.
<i>COT.vm_factory</i>	Factory for virtual machine objects.
<i>COT.vm_context_manager</i>	Context manager for virtual machine definitions.
<i>COT.xml_file</i>	Reading, editing, and writing XML files.

7.1.1 COT.vm_description module

Abstract superclass for reading, editing, and writing VMs.

<i>VMInitError</i>	Class representing errors encountered when trying to init/load a VM.
<i>VMDescription</i>	Abstract class for reading, editing, and writing VM definitions.

exception **VMInitError**

Bases: `exceptions.EnvironmentError`

Class representing errors encountered when trying to init/load a VM.

class **VMDescription** (*input_file*, *output_file=None*)

Bases: `object`

Abstract class for reading, editing, and writing VM definitions.

Properties

<i>input_file</i>	Data file to read in.
<i>output_file</i>	Filename that <i>write()</i> will output to.
<i>platform</i>	The Platform class object associated with this VM.
<i>config_profiles</i>	The list of supported configuration profiles.
<i>default_config_profile</i>	The name of the default configuration profile.
<i>environment_properties</i>	The array of environment properties.

Continued on next page

Table 7.3 – continued from previous page

<i>environment_transports</i>	The list of environment transport methods.
<i>networks</i>	The list of network names currently defined in this VM.
<i>network_descriptions</i>	The list of network descriptions currently defined in this VM.
<i>system_types</i>	List of virtual system type(s) supported by this virtual machine.
<i>version_short</i>	A short string describing the product version.
<i>version_long</i>	A long string describing the product version.

add_controller_device (*device_type*, *subtype*, *address*, *ctrl_item=None*)

Create a new IDE or SCSI controller, or update existing one.

Parameters

- **device_type** (*str*) – ‘ide’ or ‘scsi’
- **subtype** (*str*) – Subtype such as ‘virtio’ (optional)
- **address** (*int*) – Controller address such as 0 or 1 (optional)
- **ctrl_item** – Existing controller device to update (optional)

Returns New or updated controller device object

add_disk (*file_path*, *file_id*, *disk_type*, *disk=None*)

Add a new disk object to the VM or overwrite the provided one.

Parameters

- **file_path** (*str*) – Path to disk image file
- **file_id** (*str*) – Identifier string for the file/disk mapping
- **disk_type** (*str*) – ‘harddisk’ or ‘cdrom’
- **disk** – Existing disk object to overwrite

Returns New or updated disk object

add_disk_device (*disk_type*, *address*, *name*, *description*, *disk*, *file_obj*, *ctrl_item*, *disk_item=None*)

Add a new disk device to the VM or update the provided one.

Parameters

- **disk_type** (*str*) – ‘harddisk’ or ‘cdrom’
- **address** (*str*) – Address on controller, such as “1:0” (optional)
- **name** (*str*) – Device name string (optional)
- **description** (*str*) – Description string (optional)
- **disk** – Disk object to map to this device
- **file_obj** – File object to map to this device
- **ctrl_item** – Controller object to serve as parent
- **disk_item** – Existing disk device to update instead of making a new device.

Returns New or updated disk device object.

add_file (*file_path*, *file_id*, *file_obj=None*, *disk=None*)

Add a new file object to the VM or overwrite the provided one.

Parameters

- **file_path** (*str*) – Path to file to add

- **file_id** (*str*) – Identifier string for the file in the VM
- **file_obj** – Existing file object to overwrite
- **disk** – Existing disk object referencing *file*.

Returns New or updated file object

check_sanity_of_disk_device (*disk, file_obj, disk_item, ctrl_item*)

Check if the given disk is linked properly to the other objects.

Parameters

- **disk** – Disk object to validate
- **file_obj** – File object which this disk should be linked to (optional)
- **disk_item** – Disk device object which should link to this disk (optional)
- **ctrl_item** – Controller device object which should link to the *disk_item*

Raises **ValueMismatchError** – if the given items are not linked properly.

config_file_to_properties (*file_path, user_configurable=None*)

Import each line of a text file into a configuration property.

Parameters

- **file_path** (*str*) – File name to import.
- **user_configurable** (*bool*) – Should the properties be configurable at deployment time by the user?

convert_disk_if_needed (*file_path, kind*)

Convert the disk to a more appropriate format if needed.

Parameters

- **file_path** (*str*) – Image to inspect and possibly convert
- **kind** (*str*) – Image type (harddisk/cdrom).

Returns

- *file_path*, if no conversion was required
- or a file path in *output_dir* containing the converted image

create_configuration_profile (*pid, label, description*)

Create/update a configuration profile with the given ID.

Parameters

- **pid** – Profile identifier
- **label** (*str*) – Brief descriptive label for the profile
- **description** (*str*) – Verbose description of the profile

create_network (*label, description*)

Define a new network with the given label and description.

Also serves to update the description of an existing network label.

Parameters

- **label** (*str*) – Brief label for the network
- **description** (*str*) – Verbose description of the network

delete_configuration_profile (*profile*)

Delete the configuration profile with the given ID.

destroy ()

Clean up after ourselves.

Deletes `self.working_dir` and its contents.

classmethod detect_type_from_name (*filename*)

Check the given filename to see if it looks like a type we support.

Does not check file contents, as the given filename may not yet exist.

Returns A string representing a recognized and supported type of file

Raises **ValueUnsupportedError** – if we don't know how to handle this file.

find_device_location (*device*)

Find the controller type and address of a given device object.

Parameters **device** – Hardware device object.

Returns (*type*, *address*), such as ("ide", "1:0").

find_empty_drive (*disk_type*)

Find a disk device that exists but contains no data.

Parameters **disk_type** (*str*) – Disk type, such as 'cdrom' or 'harddisk'

Returns Hardware device object, or None.

find_open_controller (*controller_type*)

Find the first open slot on a controller of the given type.

Parameters **controller_type** (*str*) – 'ide' or 'scsi'

Returns (*controller_device*, *address_string*) or (None, None)

get_common_subtype (*device_type*)

Get the sub-type common to all devices of the given type.

Parameters **device_type** (*str*) – Device type such as 'ide' or 'memory'.

Returns None, if multiple such devices exist and they do not all have the same sub-type.

Returns Subtype string common to all devices of the type.

get_file_ref_from_disk (*disk*)

Get the file reference from the given opaque disk object.

Parameters **disk** – Disk object to query

Returns String that can be used to identify the file associated with this disk

get_id_from_disk (*disk*)

Get the identifier string associated with the given Disk object.

Parameters **disk** – Disk object

Return type string

get_id_from_file (*file_obj*)

Get the file ID from the given opaque file object.

Parameters **file_obj** – File object to query

Returns Identifier string associated with this object

get_nic_count (*profile_list*)

Get the number of NICs under the given profile(s).

Parameters **profile_list** (*list*) – Profile(s) of interest.

Return type dict

Returns { profile_name : nic_count }

get_path_from_file (*file_obj*)

Get the file path from the given opaque file object.

Parameters **file_obj** – File object to query

Returns Relative path to the file associated with this object

get_property_value (*key*)

Get the value of the given property.

Parameters **key** (*str*) – Property identifier

Returns Value of this property, or None

get_serial_connectivity (*profile*)

Get the serial port connectivity strings under the given profile.

Parameters **profile** (*str*) – Profile of interest.

Returns List of connectivity strings

get_serial_count (*profile_list*)

Get the number of serial ports under the given profile(s).

Return type dict

Returns { profile_name : serial_count }

get_subtype_from_device (*device*)

Get the sub-type of the given opaque device object.

Parameters **device** – Device object to query

Returns None, or string such as ‘virtio’ or ‘lsilogic’

get_type_from_device (*device*)

Get the type of the given opaque device object.

Parameters **device** – Device object to query

Returns string such as ‘ide’ or ‘memory’

info_string (*width=79, verbosity_option=None*)

Get a descriptive string summarizing the contents of this VM.

Parameters

- **width** (*int*) – Line length to wrap to where possible.
- **verbosity_option** (*str*) – ‘brief’, None (default), or ‘verbose’

Returns Wrapped, appropriately verbose string.

profile_info_string (*width=79, verbosity_option=None*)

Get a string summarizing available configuration profiles.

Parameters

- **width** (*int*) – Line length to wrap to if possible

- **verbosity_option** (*str*) – 'brief', None (default), or 'verbose'

Returns Appropriately formatted and verbose string.

remove_file (*file_obj*, *disk=None*, *disk_drive=None*)

Remove the given file object from the VM.

Parameters

- **file_obj** – File object to remove
- **disk** – Disk object referencing file
- **disk_drive** – Disk drive mapping file to a device

search_from_controller (*controller*, *address*)

From the controller type and device address, look for existing disk.

Parameters

- **controller** (*str*) – 'ide' or 'scsi'
- **address** (*str*) – Device address such as '1:0'

Returns (*file*, *disk*, *controller_device*, *disk_device*), opaque objects of which any or all may be None

search_from_file_id (*file_id*)

From the given file ID, try to find any existing objects.

Parameters **filename** (*str*) – Filename to search from

Returns (*file*, *disk*, *controller_device*, *disk_device*), opaque objects of which any or all may be None

search_from_filename (*filename*)

From the given filename, try to find any existing objects.

Parameters **filename** (*str*) – Filename to search from

Returns (*file*, *disk*, *controller_device*, *disk_device*), opaque objects of which any or all may be None

set_cpu_count (*cpus*, *profile_list*)

Set the number of CPUs.

Parameters

- **cpus** (*int*) – Number of CPUs
- **profile_list** (*list*) – Change only the given profiles

set_ide_subtype (*subtype*, *profile_list*)

Set the device subtype for the IDE controller(s).

Deprecated since version 1.5: Use `set_ide_subtypes()` instead.

Parameters

- **subtype** (*str*) – IDE subtype string
- **profile_list** (*list*) – Change only the given profiles

set_ide_subtypes (*type_list*, *profile_list*)

Set the device subtype list for the IDE controller(s).

Parameters

- **type** (*list*) – IDE subtype string list
- **profile_list** (*list*) – Change only the given profiles

set_memory (*megabytes, profile_list*)

Set the amount of RAM, in megabytes.

Parameters

- **megabytes** (*int*) – Memory value, in megabytes
- **profile_list** (*list*) – Change only the given profiles

set_nic_count (*count, profile_list*)

Set the given profile(s) to have the given number of NICs.

Parameters

- **count** (*int*) – number of NICs
- **profile_list** (*list*) – Change only the given profiles

set_nic_mac_addresses (*mac_list, profile_list*)

Set the MAC addresses for NICs under the given profile(s).

Note: If the length of `mac_list` is less than the number of NICs, will use the last entry in the list for all remaining NICs.

Parameters

- **mac_list** (*list*) – List of MAC addresses to assign to NICs
- **profile_list** (*list*) – Change only the given profiles

set_nic_names (*name_list, profile_list*)

Set the device names for NICs under the given profile(s).

Since NICs are often named sequentially, this API supports a wildcard option for the final element in `name_list` which can be expanded to automatically assign sequential NIC names. The syntax for the wildcard option is { followed by a number (indicating the starting index for the name) followed by }. Examples:

`["eth{0}"]` Expands to `["eth0", "eth1", "eth2", ...]`

`["mgmt0" "eth{10}"]` Expands to `["mgmt0", "eth10", "eth11", "eth12", ...]`

Parameters

- **name_list** (*list*) – List of names to assign.
- **profile_list** (*list*) – Change only the given profiles

set_nic_networks (*network_list, profile_list*)

Set the NIC to network mapping for NICs under the given profile(s).

Note: If the length of `network_list` is less than the number of NICs, will use the last entry in the list for all remaining NICs.

Parameters

- **network_list** (*list*) – List of networks to map NICs to
- **profile_list** (*list*) – Change only the given profiles

set_nic_type (*nic_type*, *profile_list*)

Set the hardware type for NICs.

Deprecated since version 1.5: Use `set_nic_types()` instead.

Parameters

- **nic_type** (*str*) – NIC hardware type
- **profile_list** (*list*) – Change only the given profiles.

set_nic_types (*type_list*, *profile_list*)

Set the hardware type(s) for NICs.

Parameters

- **type_list** (*list*) – NIC hardware type(s)
- **profile_list** (*list*) – Change only the given profiles.

set_property_value (*key*, *value*, *user_configurable*=None, *property_type*=None, *label*=None, *description*=None)

Set the value of the given property (converting value if needed).

Parameters

- **key** (*str*) – Property identifier
- **value** – Value to set for this property
- **user_configurable** (*bool*) – Should this property be configurable at deployment time by the user?
- **property_type** (*str*) – Value type - ‘string’ or ‘boolean’
- **label** (*str*) – Brief explanatory label for this property
- **description** (*str*) – Detailed description of this property

Returns the (converted) value that was set.

set_scsi_subtype (*subtype*, *profile_list*)

Set the device subtype for the SCSI controller(s).

Deprecated since version 1.5: Use `set_scsi_subtypes()` instead.

Parameters

- **subtype** (*str*) – SCSI subtype string
- **profile_list** (*list*) – Change only the given profiles

set_scsi_subtypes (*type_list*, *profile_list*)

Set the device subtype list for the SCSI controller(s).

Parameters

- **type_list** (*list*) – SCSI subtype string list
- **profile_list** (*list*) – Change only the given profiles

set_serial_connectivity (*conn_list*, *profile_list*)

Set the serial port connectivity under the given profile(s).

Parameters

- **conn_list** (*list*) – List of connectivity strings
- **profile_list** (*list*) – Change only the given profiles

set_serial_count (*count*, *profile_list*)

Set the given profile(s) to have the given number of NICs.

Parameters

- **count** (*int*) – Number of serial ports
- **profile_list** (*list*) – Change only the given profiles

validate_hardware ()

Check sanity of hardware properties for this VM/product/platform.

Returns True if hardware is sane, False if not.

write ()

Write the VM description to *output_file*, if any.

config_profiles

The list of supported configuration profiles.

If there are no profiles defined, returns an empty list. If there is a default profile, it will be first in the list.

default_config_profile

The name of the default configuration profile.

Returns Profile name or None if none are defined.

environment_properties

The array of environment properties.

Returns Array of dicts (one per property) with the keys "key", "value", "qualifiers", "type", "label", and "description".

environment_transports

The list of environment transport methods.

Return type list[str]

input_file

Data file to read in.

network_descriptions

The list of network descriptions currently defined in this VM.

Return type list[str]

networks

The list of network names currently defined in this VM.

Return type list[str]

output_file

Filename that *write* () will output to.

platform

The Platform class object associated with this VM.

GenericPlatform or a more specific subclass if recognized as such.

product_class

The product class identifier, such as com.cisco.csr1000v.

system_types

List of virtual system type(s) supported by this virtual machine.

verbosity_options = {'verbose': 2, 'brief': 0, None: 1}

version_long

A long string describing the product version.

version_short

A short string describing the product version.

7.1.2 COT.vm_factory module

Factory for virtual machine objects.

class VMFactory

Bases: object

Creates a VMDescription instance from a specified input file.

classmethod create (*input_file*, *output_file*)

Create an appropriate VMDescription subclass instance from a file.

Raises

- **VMInitError** – if no appropriate class is identified
- **VMInitError** – if the selected subclass raises a ValueUnsupportedError while loading the file.

Parameters

- **input_file** (*str*) – File to read VM description from
- **output_file** (*str*) – File to write to when finished (optional)

Return type instance of VMDescription or appropriate subclass

7.1.3 COT.vm_context_manager module

Context manager for virtual machine definitions.

class VMContextManager (*input_file*, *output_file*)

Bases: object

Context manager for virtual machine definitions.

When the context manager exits, unless an error occurred, the virtual machine's `write()` method is called. Regardless of whether an error occurred, the virtual machine's `destroy()` method is then called.

Use as follows:

```
with VMContextManager(input_file, output_file) as vm:
    vm.foo()
    vm.bar()
```

7.1.4 COT.xml_file module

Reading, editing, and writing XML files.

class XML (*xml_file*)

Bases: `object`

Class capable of reading, editing, and writing XML files.

classmethod add_child (*parent, new_child, ordering=None, known_namespaces=None*)

Add the given child element under the given parent element.

Parameters

- **parent** (*xml.etree.ElementTree.Element*) – Parent element
- **new_child** (*xml.etree.ElementTree.Element*) – Child element to attach
- **ordering** (*list*) – (Optional) List describing the expected ordering of child tags under the parent; if a new child element is created, its placement under the parent will respect this sequence.
- **known_namespaces** (*list*) – (Optional) List of well-understood XML namespaces. If a new child is created, and `ordering` is given, any tag (new or existing) that is encountered but not accounted for in `ordering` will result in COT logging a warning **iff** the unaccounted-for tag is in a known namespace.

classmethod find_all_children (*parent, tag, attrib=None*)

Find all matching child elements under the specified parent element.

Parameters

- **parent** (*xml.etree.ElementTree.Element*) – Parent element
- **tag** (*string or iterable*) – Child tag (or list of tags) to match on
- **attrib** (*dict*) – Child attributes to match on

Return type list of `xml.etree.ElementTree.Element` instances

classmethod find_child (*parent, tag, attrib=None, required=False*)

Find the unique child element under the specified parent element.

Raises

- **LookupError** – if more than one matching child is found
- **KeyError** – if no matching child is found and `required` is `True`

Parameters

- **parent** (*xml.etree.ElementTree.Element*) – Parent element
- **tag** (*str*) – Child tag to match on
- **attrib** (*dict*) – Child attributes to match on
- **required** (*boolean*) – Whether to raise an error if no child exists

Return type `xml.etree.ElementTree.Element`

classmethod get_ns (*text*)

Get the namespace prefix from an XML element or attribute name.

classmethod set_or_make_child (*parent, tag, text=None, attrib=None, ordering=None, known_namespaces=None*)

Update or create a child element under the specified parent element.

Parameters

- **parent** (*xml.etree.ElementTree.Element*) – Parent element

- **tag** (*str*) – Child element text tag to find or create
- **text** (*str*) – Value to set the child’s text attribute to
- **attrib** (*dict*) – Dict of child attributes to match on while searching and set in the final child element
- **ordering** (*list*) – See `add_child()`
- **known_namespaces** (*list*) – See `add_child()`

Returns New or updated child Element.

Return type `xml.etree.ElementTree.Element`

classmethod strip_ns (*text*)

Remove a namespace prefix from an XML element or attribute name.

write_xml (*xml_file*)

Write pretty XML out to the given file.

Parameters **xml_file** (*str*) – Filename to write to

xml_reindent (*parent, depth*)

Recursively add indentation to XML to make it look nice.

Parameters

- **parent** (`xml.etree.ElementTree.Element`) – Current parent element
- **depth** (*int*) – How far down the rabbit hole we have recursed. Increments by 2 for each successive level of nesting.

register_namespace (*prefix, uri*)

Record a particular mapping between a namespace prefix and URI.

Parameters

- **prefix** (*str*) – Namespace prefix such as “ovf”
- **uri** (*str*) – Namespace URI such as “<http://schemas.dmtf.org/ovf/envelope/1>”

7.2 Command modules

<code>COT.submodule</code>	Parent classes for implementing COT subcommands.
<code>COT.add_disk</code>	Module for adding disks to VMs.
<code>COT.add_file</code>	Module for adding files to VM definitions.
<code>COT.deploy</code>	Module for deploying VM descriptions to a hypervisor to instantiate VMs.
<code>COT.deploy_esxi</code>	Module for deploying VMs to ESXi, vCenter, and vSphere.
<code>COT.edit_hardware</code>	Module for editing hardware details of a VM.
<code>COT.edit_product</code>	Module for editing product information in a VM description.
<code>COT.edit_properties</code>	Module for managing VM environment configuration properties.
<code>COT.help</code>	Provide ‘help’ keyword for COT CLI.
<code>COT.info</code>	Implements “info” subcommand.
<code>COT.inject_config</code>	Implements “inject-config” command.
<code>COT.install_helpers</code>	Implements “install-helpers” command.
<code>COT.remove_file</code>	Module for removing files from VM definitions.

7.2.1 COT.submodule module

Parent classes for implementing COT subcommands.

Classes

<i>COTGenericSubmodule</i>	Abstract interface for COT command submodules.
<i>COTReadOnlySubmodule</i>	Class for submodules that do not modify the OVF, such as ‘deploy’.
<i>COTSubmodule</i>	Class for submodules that read and write the OVF.

class **COTGenericSubmodule** (*ui*)

Bases: object

Abstract interface for COT command submodules.

Attributes: *vm*, *UI*

Note: Generally a command should not inherit directly from this class, but should instead subclass *COTReadOnlySubmodule* or *COTSubmodule* as appropriate.

create_subparser ()

Add subparser for the CLI of this submodule.

destroy ()

Destroy any VM associated with this submodule.

finished ()

Do any final actions before being destroyed.

This class does nothing; subclasses may choose to do things like write their VM state out to a file.

ready_to_run ()

Check whether the module is ready to *run* ().

Returns (True, *ready_message*) or (False, *reason_why_not*)

run ()

Do the actual work of this submodule.

Raises *InvalidInputError* if *ready_to_run* () reports False

UI = None

User interface instance (UI or subclass).

vm = None

Virtual machine description (VMDescription).

class **COTReadOnlySubmodule** (*ui*)

Bases: *COT.submodule.COTGenericSubmodule*

Class for submodules that do not modify the OVF, such as ‘deploy’.

Inherited attributes: *vm*, *UI*

Attributes: *package*

ready_to_run ()

Check whether the module is ready to *run* ().

Returns (True, *ready_message*) or (False, *reason_why_not*)

package

VM description file to read from.

Calls `COT.vm_factory.VMFactory.create()` to instantiate `self.vm` from the provided file.

Raises `InvalidInputError` if the file does not exist.

class COTSubmodule(ui)

Bases: `COT.submodule.COTGenericSubmodule`

Class for submodules that read and write the OVF.

Inherited attributes: `vm`, `UI`

Attributes: `package`, `output`

finished()

Write the current VM state out to disk if requested.

ready_to_run()

Check whether the module is ready to `run()`.

Returns (True, `ready_message`) or (False, `reason_why_not`)

run()

Do the actual work of this submodule.

If `output` was not previously set, automatically sets it to the value of `PACKAGE`.

Raises `InvalidInputError` if `ready_to_run()` reports False

output

Output file for this submodule.

If the specified file already exists, will prompt the user (`confirm_or_die()`) to confirm overwriting the existing file.

package

VM description file to read (and possibly write).

Calls `COT.vm_factory.VMFactory.create()` to instantiate `self.vm` from the provided file.

Raises `InvalidInputError` if the file does not exist.

7.2.2 COT.add_disk module

Module for adding disks to VMs.

Functions

<code>add_disk_worker</code>	Worker function for actually adding the disk.
<code>confirm_elements</code>	Get user confirmation of any risky or unusual operations.
<code>guess_controller_type</code>	If a controller type wasn't specified, try to guess from context.
<code>guess_disk_type_from_extension</code>	Guess the disk type (harddisk/cdrom) from the disk file name.
<code>search_for_elements</code>	Search for a unique set of objects based on the given criteria.
<code>validate_elements</code>	Validate any existing file, disk, controller item, and disk item.
<code>validate_controller_address</code>	Check validity of the given address string for the given controller.

Classes

<code>COTAddDisk</code>	Add or replace a disk in a virtual machine.
-------------------------	---

class COTAddDisk (ui)

Bases: *COT.submodule.COTSubmodule*

Add or replace a disk in a virtual machine.

Inherited attributes: UI, package, output

Attributes: *disk_image*, *type*, *file_id*, *controller*, *subtype*, *address*, *diskname*, *description*

create_subparser ()

Create ‘add-disk’ CLI subparser.

ready_to_run ()

Check whether the module is ready to *run ()*.

Returns (True, *ready_message*) or (False, *reason_why_not*)

run ()

Do the actual work of this submodule.

Raises *InvalidInputError* – if *ready_to_run ()* reports False

address

Disk device address on controller (1:0, etc.).

Raises *InvalidInputError*, see *validate_controller_address ()*

controller

Disk controller type (ide, scsi).

Raises *InvalidInputError*, see *validate_controller_address ()*

description = None

Description of the disk.

disk_image

Path to disk image file to add to the VM.

Raises *InvalidInputError* if the file does not exist.

disk_type = None

Disk type (‘harddisk’ or ‘cdrom’).

diskname = None

Name string for the disk.

file_id = None

File identifier to map disk to file.

subtype = None

Controller subtype, such as “virtio”.

add_disk_worker (vm, ui, disk_image, disk_type=None, file_id=None, controller=None, subtype=None, address=None, diskname=None, description=None)

Worker function for actually adding the disk.

All parameters except *vm*, *ui*, and *disk_image* are optional and will be automatically determined by COT if unspecified.

Parameters

- **vm** (OVF or other *VMDescription* subclass) – The virtual machine being edited.
- **ui** (instance of *UI* or subclass.) – User interface in effect.
- **disk_image** (*str*) – path to disk image to add to the VM.

- **disk_type** (*str*) – Disk type: 'cdrom' or 'harddisk'. If not specified, will be derived automatically from the disk_image file name extension.
- **file_id** (*str*) – Identifier of the disk file in the VM. If not specified, the VM will automatically derive an appropriate value.
- **controller** (*str*) – Disk controller type: 'ide' or 'scsi'. If not specified, will be derived from the *type* and the *platform* of the given *vm*.
- **subtype** (*str*) – Controller subtype ('virtio', 'lsilogic', etc.)
- **address** (*str*) – Disk device address on its controller (such as '1:0'). If this matches an existing disk device, that device will be overwritten. If not specified, the first available address not already occupied by an existing device will be selected.
- **diskname** (*str*) – Name for disk device
- **description** (*str*) – Description of disk device

confirm_elements (*vm, ui, file_obj, disk_image, disk_obj, disk_item, disk_type, controller, ctrl_item, subtype*)

Get user confirmation of any risky or unusual operations.

guess_controller_type (*vm, ctrl_item, disk_type*)

If a controller type wasn't specified, try to guess from context.

guess_disk_type_from_extension (*disk_file*)

Guess the disk type (harddisk/cdrom) from the disk file name.

search_for_elements (*vm, disk_file, file_id, controller, address*)

Search for a unique set of objects based on the given criteria.

A disk is defined by up to four different sections in the OVF:

File (references the actual disk image file) Disk (references the File, only used for HD not CD-ROM) Item (defines the SCSI/IDE controller) Item (defines the disk drive, links to controller and File or Disk)

For each of these four sections, we need to know whether to add a new one or overwrite an existing one. Depending on the user arguments, we can do this by as many as three different approaches:

1. Check whether the DISK_IMAGE file name matches an existing File in the OVF (and from there, find the associated Disk and Items)
2. Check whether the file-id matches an existing File and/or Disk in the OVF (and from there, find the associated Items)
3. Check whether controller type and/or device address match existing Items in the OVF (and from there, find the associated Disk and/or File)

Where it gets extra fun is if the user has specified more than one of the above arguments - in which case we need to make sure that all relevant approaches agree on what sections we're talking about...

Raises ValueMismatchError – if the criteria select a non-unique set.

Returns (file_object, disk_object, controller_item, disk_item)

validate_controller_address (*controller, address*)

Check validity of the given address string for the given controller.

Helper method for the controller/address setters.

Parameters

- **controller** (*str*) – 'ide' or 'scsi'
- **address** (*str*) – A string like '0:0' or '2:10'

Raises *InvalidInputError* if the address/controller combo is invalid.

validate_elements (*vm, file_obj, disk_obj, disk_item, ctrl_item, file_id, ctrl_type*)
Validate any existing file, disk, controller item, and disk item.

Raises *ValueMismatchError* – if the search criteria select a non-unique set.

7.2.3 COT.add_file module

Module for adding files to VM definitions.

<i>COTAddFile</i> (<i>ui</i>)	Add a file (such as a README) to the package.
---------------------------------	---

class *COTAddFile* (*ui*)

Bases: *COT.submodule.COTSubmodule*

Add a file (such as a README) to the package.

Inherited attributes: *UI, package, output*

Attributes: *file, file_id*

create_subparser ()

Create ‘add-file’ CLI subparser.

ready_to_run ()

Check whether the module is ready to *run* ().

Returns (*True, ready_message*) or (*False, reason_why_not*)

run ()

Do the actual work of this submodule.

Raises *InvalidInputError* – if *ready_to_run* () reports *False*

file

File to be added to the package.

Raises *InvalidInputError* if the file does not exist.

file_id = None

File identifier string.

7.2.4 COT.deploy module

Module for deploying VM descriptions to a hypervisor to instantiate VMs.

Classes

<i>COTDeploy</i>	Semi-abstract class for submodules used to deploy a VM to a hypervisor.
<i>SerialConnection</i>	Generic class defining a serial port connection.

class *COTDeploy* (*ui*)

Bases: *COT.submodule.COTReadOnlySubmodule*

Semi-abstract class for submodules used to deploy a VM to a hypervisor.

Provides some baseline parameters and input validation that are expected to be common across all concrete subclasses.

Inherited attributes: `UI`, `package`,

Attributes: `generic_parser`, `parser`, `subparsers`, `hypervisor`, `configuration`, `username`, `password`, `power_on`, `vm_name`, `network_map`

create_subparser()

Create 'deploy' CLI subparser if it doesn't already exist.

Note: Unlike most submodules, this one has subparsers of its own - '`cot deploy PACKAGE <hypervisor>`' so subclasses of this module should call `super().create_subparser()` (to create the main 'deploy' subparser if it doesn't already exist) then call `self.UI.add_parser(..., parent=self.subparsers, ...)` to add their own sub-subparser.

ready_to_run()

Check whether the module is ready to `run()`.

Returns (True, `ready_message`) or (False, `reason_why_not`)

run()

Do the actual work of this submodule.

configuration

VM configuration profile to use for deployment.

Raise `InvalidInputError` if not a profile defined in the VM.

generic_parser = None

Generic parser object providing args that most subclasses will use.

Subclasses can call `self.subparsers.add_parser(parents=[self.generic_parser])` to automatically inherit this set of args

hypervisor

Hypervisor to deploy to.

Raise `InvalidInputError` if not a recognized value.

network_map

Mapping of network names to networks.

password = None

Server login password.

power_on

Whether to automatically power on the VM after deployment.

serial_connection

Mapping of serial ports to various connection types.

subparsers = None

Subparser grouping for hypervisor-specific sub-subparsers.

Subclasses should generally have their `create_subparser()` implementations create their sub-subparsers with `parent=subparsers`.

username = None

Server login username.

vm_name = None

Name of the created virtual machine

class SerialConnection (*kind, value, options*)

Bases: `object`

Generic class defining a serial port connection.

classmethod from_cli_string (*cli_string*)

Parse a string 'kind:value[,opts]' to build a SerialConnection.

Based on the QEMU CLI for serial ports.

classmethod validate_kind (*kind*)

Validate the connection type string and munge it as needed.

Parameters *kind* (*str*) – Connection type string, possibly in need of munging.

Returns A valid type string

Raises `ValueUnsupportedError` – if type string is not recognized as valid

classmethod validate_options (*kind, _value, options*)

Check that the given set of options are valid for this connection.

Parameters

- *kind* (*str*) – Validated 'kind' string.
- *_value* (*str*) – Validated 'value' string. Currently unused.
- *options* (*dict*) – Input options dictionary.

Returns validated options dict

Raises `InvalidInputError` – if options are not valid.

classmethod validate_value (*kind, value*)

Check that the given value is valid for the given connection kind.

Parameters

- *kind* (*str*) – Connection type, valid per `validate_kind()`.
- *value* (*str*) – Connection value such as '/dev/ttyS0' or '1.1.1.1:80'

Returns Munged value string.

Raises `InvalidInputError` – if value string is not recognized as valid

7.2.5 COT.deploy_esxi module

Module for deploying VMs to ESXi, vCenter, and vSphere.

Functions

`get_object_from_connection` Look up an object by name.

Classes

<code>COTDeployESXi</code>	Submodule for deploying VMs on ESXi and VMware vCenter/vSphere.
<code>SmarterConnection</code>	A smarter version of pyVmomi's SmartConnection context manager.
<code>PyVmomiVMReconfigSpec</code>	Context manager for reconfiguring an ESXi VM using PyVmomi.

class COTDeployESXi (*ui*)

Bases: *COT.deploy.COTDeploy*

Submodule for deploying VMs on ESXi and VMware vCenter/vSphere.

Inherited attributes: *UI*, *package*, *generic_parser*, *parser*, *subparsers*, *hypervisor*, *configuration*, *username*, *password*, *power_on*, *vm_name*, *network_map*, *serial_connection*

Attributes: *locator*, *datastore*, *ovftool_args*

create_subparser()

Add subparser for the CLI of this submodule.

This will create the shared *parser*, then create our own sub-subparser under *subparsers*.

fixup_ovftool_args (*ovftool_args*, *target*)

Make any needed modifications to the ovftool arguments.

Parameters

- **ovftool_args** (*list*) – Any existing ovftool arguments to begin with.
- **target** (*str*) – deployment target URI

Returns Updated ovftool arguments

fixup_serial_ports()

Use PyVmomi to create and configure serial ports for the new VM.

ready_to_run()

Check whether the module is ready to *run()*.

Returns (True, *ready_message*) or (False, *reason_why_not*)

run()

Do the actual work of this submodule - deploying to ESXi.

Raises **InvalidInputError** – if *ready_to_run()* reports False

datastore = None

ESXi datastore to deploy to.

host = None

vSphere host to deploy to - set implicitly by self.locator.

locator

Target vSphere locator.

ovftool_args

List of CLI arguments to pass through to ovftool.

serial_connection

Mapping of serial ports to various connection types.

server = None

vCenter server or vSphere host - set implicitly by self.locator.

class PyVmomiVMReconfigSpec (*conn*, *vm_name*)

Bases: *object*

Context manager for reconfiguring an ESXi VM using PyVmomi.

class SmarterConnection (*ui*, *server*, *username*, *password*, *port=443*)

Bases: *pyVim.connect.SmartConnection*

A smarter version of pyVmomi's SmartConnection context manager.

static `unwrap_connection_error(outer_e)`

Extract inner attributes from a `ConnectionError`.

`ConnectionError` often wraps another exception with more context; this function dives inside the `ConnectionError` to find that context.

Parameters `outer_e` (`ConnectionError`) – `ConnectionError` to unwrap

Returns extracted (errno, inner_message)

get_object_from_connection (`conn`, `vimtype`, `name`)

Look up an object by name.

7.2.6 COT.edit_hardware module

Module for editing hardware details of a VM.

Functions

<code>expand_list_wildcard</code>	Expand a list containing a wildcard to the desired length.
<code>guess_list_wildcard</code>	Inverse of <code>expand_list_wildcard()</code> .

Classes

<code>COTEditHardware</code>	Edit hardware information (CPUs, RAM, NICs, etc.).
------------------------------	--

class `COTEditHardware(ui)`

Bases: `COT.submodule.COTSubmodule`

Edit hardware information (CPUs, RAM, NICs, etc.).

Inherited attributes: `UI`, `package`, `output`

Attributes: `profiles`, `delete_all_other_profiles`, `cpus`, `memory`, `nics`, `nic_types`, `mac_addresses_list`, `nic_networks`, `nic_names`, `network_descriptions`, `serial_ports`, `serial_connectivity`, `scsi_subtypes`, `ide_subtypes`, `virtual_system_type`

create_subparser()

Create ‘edit-hardware’ CLI subparser.

ready_to_run()

Check whether the module is ready to `run()`.

Returns (True, ready_message) or (False, reason_why_not)

run()

Do the actual work of this submodule.

Raises `InvalidInputError` – if `ready_to_run()` reports False

MEMORY_REGEX = `‘^\s*(\d+)\s*([mMgG])?i?[bB]?\s*$’`

cpus

Number of CPUs to set.

delete_all_other_profiles = None

Delete all profiles other than those set in `profiles`.

ide_subtype

IDE controller subtype string to set.

Deprecated since version 1.5: Use *ide_subtypes* instead.

ide_subtypes

IDE controller subtype string(s) to set.

mac_addresses_list = None

List of MAC addresses to set.

memory

Amount of RAM (in megabytes) to set.

network_descriptions = None

List of network description strings.

Can use wildcards as described in *expand_list_wildcard()*.

nic_names = None

List of NIC name strings.

Can use wildcards as described in *expand_list_wildcard()*.

nic_networks = None

List of NIC-to-network mappings.

Can use wildcards as described in *expand_list_wildcard()*.

nic_type

NIC type string to set.

Deprecated since version 1.5: Use *nic_types* instead.

nic_types

List of NIC type strings to set.

nics

Number of NICs to set.

profiles = None

Configuration profile(s) to edit.

scsi_subtype

SCSI controller subtype string to set.

Deprecated since version 1.5: Use *scsi_subtypes* instead.

scsi_subtypes

SCSI controller subtype string(s) to set.

serial_connectivity = None

List of serial connection strings.

serial_ports

Serial port count to set.

virtual_system_type = None

Virtual system type

expand_list_wildcard (*name_list*, *length*, *quiet=False*)

Expand a list containing a wildcard to the desired length.

Since various items (NIC names, network names, etc.) are often named or numbered sequentially, we provide this API to allow the user to specify a wildcard value to permit automatically expanding a list of input strings to

the desired length. The syntax for the wildcard option is { followed by a number (indicating the starting index for the name) followed by }. Examples:

```
>>> expand_list_wildcard(None, 3)
[]
>>> expand_list_wildcard(["eth{0}"], 3)
['eth0', 'eth1', 'eth2']
>>> expand_list_wildcard(["mgmt0", "eth{10}"], 4)
['mgmt0', 'eth10', 'eth11', 'eth12']
```

Parameters

- **name_list** (*list*) – List of names to assign, or None
- **length** (*list*) – Length to expand to
- **quiet** (*bool*) – Silence usual log messages generated by this function.

Returns Expanded list, or empty list if name_list is None or empty.

guess_list_wildcard(*known_values*)

Inverse of `expand_list_wildcard()`. Guess the wildcard for a list.

Examples:

```
>>> guess_list_wildcard(['foo', 'bar', 'baz'])
>>> guess_list_wildcard(['foo1', 'foo2', 'foo3'])
['foo{1}']
>>> guess_list_wildcard(['foo', 'bar', 'baz3', 'baz4', 'baz5'])
['foo', 'bar', 'baz{3}']
>>> guess_list_wildcard(['Eth0/1', 'Eth0/2', 'Eth0/3'])
['Eth0/{1}']
>>> guess_list_wildcard(['Eth0/0', 'Eth1/0', 'Eth2/0'])
['Eth{0}/0']
>>> guess_list_wildcard(['fake1', 'fake2', 'real4', 'real5'])
['fake1', 'fake2', 'real{4}']
```

Parameters **known_values** (*list*) – Values to guess from

Returns Guessed wildcard list, or None if unable to guess

7.2.7 COT.edit_product module

Module for editing product information in a VM description.

Classes

<i>COTEditProduct</i>	Edit product, vendor, and version information strings.
-----------------------	--

class COTEditProduct(*ui*)

Bases: *COT.submodule.COTSubmodule*

Edit product, vendor, and version information strings.

Inherited attributes: UI, package, output

Attributes: *product_class product vendor version, full_version product_url vendor_url application_url*

create_subparser()
Create 'edit-product' CLI subparser.

ready_to_run()
Check whether the module is ready to *run()*.

Returns (True, ready_message) or (False, reason_why_not)

run()
Do the actual work of this submodule.

Raises **InvalidInputError** – if *ready_to_run()* reports False

application_url = None
Application URL string.

full_version = None
Long version string.

product = None
Product description string.

product_class = None
Product class identifier.

product_url = None
Product URL string.

vendor = None
Vendor string.

vendor_url = None
Vendor URL string.

version = None
Short version string.

7.2.8 COT.edit_properties module

Module for managing VM environment configuration properties.

Classes

<i>COTEditProperties</i>	Edit OVF environment XML properties.
--------------------------	--------------------------------------

class COTEditProperties(ui)
Bases: *COT.submodule.COTSubmodule*
Edit OVF environment XML properties.
Inherited attributes: UI, package, output
Attributes: *config_file, properties, transports, user_configurable*

create_subparser()
Create 'edit-properties' CLI subparser.

edit_properties_interactive()
Present an interactive UI for the user to edit properties.

ready_to_run()
Check whether the module is ready to *run()*.

Returns (True, ready_message) or (False, reason_why_not)

run()
Do the actual work of this submodule.

Raises `InvalidInputError` – if `ready_to_run()` reports False

config_file
Path to plaintext file to read configuration lines from.

Raise `InvalidInputError` if the file does not exist.

descriptions = None
List of description strings to set for updated properties.

labels = None
List of label strings to set for the properties being updated.

properties
List of property (key, value, type) tuples to update.

transports
Transport mechanism(s) for environment properties..

user_configurable = None
Value to set the user_configurable flag on properties we edit.

7.2.9 COT.help module

Provide ‘help’ keyword for COT CLI.

class COTHelp(ui)
Bases: `COT.submodule.COTGenericSubmodule`

Provide ‘help <subcommand>’ syntax.

Inherited attributes: UI

Attributes: `subcommand`

create_subparser()
Create ‘help’ CLI subparser.

run()
Display the help menu for the specified subcommand.

subcommand
CLI subcommand to give help for.

If None, then help will be displayed for the COT global parser.

7.2.10 COT.info module

Implements “info” subcommand.

class COTInfo(ui)
Bases: `COT.submodule.COTGenericSubmodule`

Display VM information string.

Inherited attributes: UI

Attributes: `package_list`, `verbosity`

create_subparser()

Create ‘info’ CLI subparser.

ready_to_run()

Check whether the module is ready to *run()*.

Returns (True, ready_message) or (False, reason_why_not)

run()

Do the actual work of this submodule.

Raises **InvalidInputError** – if *ready_to_run()* reports False

package_list

List of VM definitions to get information for.

verbosity

Verbosity of information displayed.

7.2.11 COT.inject_config module

Implements “inject-config” command.

class COTInjectConfig(ui)

Bases: *COT.submodule.COTSubmodule*

Wrap configuration file(s) into a disk image embedded into the VM.

Inherited attributes: UI, package, output

Attributes: *config_file*, *secondary_config_file*

create_subparser()

Create ‘inject-config’ CLI subparser.

ready_to_run()

Check whether the module is ready to *run()*.

Returns (True, ready_message) or (False, reason_why_not)

run()

Do the actual work of this submodule.

Raises **InvalidInputError** – if *ready_to_run()* reports False

config_file

Primary configuration file.

Raises

- **InvalidInputError** – if the file does not exist
- **InvalidInputError** – if the *platform described by :attr:‘package* doesn’t support configuration files.

secondary_config_file

Secondary configuration file.

Raises

- **InvalidInputError** – if the file does not exist
- **InvalidInputError** – if the platform described by package doesn’t support secondary configuration files.

7.2.12 COT.install_helpers module

Implements “install-helpers” command.

```
class COTInstallHelpers (ui)
    Bases: COT.submodule.COTGenericSubmodule

    Install all helper tools that COT requires.

    create_subparser ()
        Create ‘install-helpers’ CLI subparser.

    install_helper (helper)
        Install the given helper module.

        Returns (result, message)

    manpages_helper ()
        Verify or install COT’s manual pages.

        Returns (result, message)

    run ()
        Verify all helper tools and install any that are missing.

guess_manpath ()
    Guess the directory path where man pages should be installed.

install_manpages (man_dir)
    Install COT’s manual pages.

    Returns (result, message)

verify_manpages (man_dir)
    Verify installation of COT’s manual pages.

    Returns (result, message)
```

7.2.13 COT.remove_file module

Module for removing files from VM definitions.

COTRemoveFile(ui) Remove a file (such as a README) from the package.

```
class COTRemoveFile (ui)
    Bases: COT.submodule.COTSubmodule

    Remove a file (such as a README) from the package.

    Inherited attributes:

    UI, package, output

    Attributes: file_path, file_id

    create_subparser ()
        Create ‘remove-file’ CLI subparser.

    ready_to_run ()
        Check whether the module is ready to run ().

        Returns (True, ready_message) or (False, reason_why_not)
```

run()

Do the actual work of this submodule.

Raises **InvalidInputError** – if `ready_to_run()` reports `False`

file_id = None

File identifier to be removed from the package.

file_path = None

File name or path to be removed from the package.

7.3 Helper library modules

<code>COT.data_validation</code>	Various helpers for data sanity checks.
<code>COT.file_reference</code>	Wrapper classes to abstract away differences between file sources.
<code>COT.platforms</code>	Handles behavior that varies between guest platforms.

7.3.1 COT.data_validation module

Various helpers for data sanity checks.

Exceptions

<code>InvalidInputError</code>	Miscellaneous error during validation of user input.
<code>ValueMismatchError</code>	Values which were expected to be equal turned out to be not equal.
<code>ValueUnsupportedError</code>	An unsupported value was provided.
<code>ValueTooLowError</code>	A numerical input was less than the lowest supported value.
<code>ValueTooHighError</code>	A numerical input was higher than the highest supported value.

Functions

<code>alphanum_split</code>	Split the key into a list of [text, int, text, int, ...].
<code>canonicalize_helper</code>	Try to find a mapping of input to output.
<code>canonicalize_ide_subtype</code>	Try to convert the given IDE controller string to a canonical form.
<code>canonicalize_nic_subtype</code>	Try to convert the given NIC subtype string to a canonical form.
<code>canonicalize_scsi_subtype</code>	Try to convert the given SCSI controller string to a canonical form.
<code>check_for_conflict</code>	Make sure the list does not contain references to more than one object.
<code>device_address</code>	Parser helper function for device address arguments.
<code>mac_address</code>	Parser helper function for MAC address arguments.
<code>match_or_die</code>	Make sure “first” and “second” are equal or raise an error.
<code>natural_sort</code>	Sort the given list “naturally” rather than in ASCII order.
<code>no_whitespace</code>	Parser helper function for arguments not allowed to contain whitespace.
<code>non_negative_int</code>	Parser helper function for integer arguments that must be 0 or more.
<code>positive_int</code>	Parser helper function for integer arguments that must be 1 or more.
<code>to_string</code>	Get string representation of an object, special-case for XML Element.
<code>validate_int</code>	Parser helper function for validating integer arguments in a range.
<code>truth_value</code>	Parser helper function for truth values like ‘0’, ‘y’, or ‘false’.

Constants

NIC_TYPES List of NIC type strings recognized as canonical.

exception InvalidInputErrorBases: `exceptions.ValueError`

Miscellaneous error during validation of user input.

exception ValueMismatchErrorBases: `exceptions.ValueError`

Values which were expected to be equal turned out to be not equal.

exception ValueTooHighError (*value_type, actual, expected*)Bases: `COT.data_validation.ValueUnsupportedError`

A numerical input was higher than the highest supported value.

Variables

- **value_type** – descriptive string
- **actual_value** – invalid value that was provided
- **expected_value** – maximum supported value

exception ValueTooLowError (*value_type, actual, expected*)Bases: `COT.data_validation.ValueUnsupportedError`

A numerical input was less than the lowest supported value.

Variables

- **value_type** – descriptive string
- **actual_value** – invalid value that was provided
- **expected_value** – minimum supported value

exception ValueUnsupportedError (*value_type, actual, expected*)Bases: `COT.data_validation.InvalidInputError`

An unsupported value was provided.

Variables

- **value_type** – descriptive string
- **actual_value** – invalid value that was provided
- **expected_value** – expected (valid) value or values (item or list)

alphanum_split (*key*)

Split the key into a list of [text, int, text, int, ...].

canonicalize_helper (*label, user_input, mappings, re_flags=0*)

Try to find a mapping of input to output.

Parameters

- **label** (*str*) – Label to use in any error raised
- **user_input** (*str*) – User-provided string
- **mappings** (*list*) – List of (*expr*, *canonical*) pairs for mapping.
- **re_flags** – `re.IGNORECASE`, etc. if desired

Returns The canonical string

Raises **ValueUnsupportedError** – If no `expr` in mappings matches input.

canonicalize_ide_subtype (*subtype*)

Try to convert the given IDE controller string to a canonical form.

Parameters **subtype** (*str*) – User-provided string

Returns

The canonical string, one of:

- `PIIX4`
- `virtio`

Raises **ValueUnsupportedError** – If the canonical string cannot be determined

canonicalize_nic_subtype (*subtype*)

Try to convert the given NIC subtype string to a canonical form.

Parameters **subtype** (*str*) – User-provided string

Returns The canonical string, one of `NIC_TYPES`

Raises **ValueUnsupportedError** – If the canonical string cannot be determined

See also:

`COT.platforms.GenericPlatform.validate_nic_type()`

canonicalize_scsi_subtype (*subtype*)

Try to convert the given SCSI controller string to a canonical form.

Parameters **subtype** (*str*) – User-provided string

Returns

The canonical string, one of:

- `buslogic`
- `lsilogic`
- `lsilogicsas`
- `virtio`
- `VirtualSCSI`

Raises **ValueUnsupportedError** – If the canonical string cannot be determined

check_for_conflict (*label*, *li*)

Make sure the list does not contain references to more than one object.

Parameters

- **label** (*str*) – Descriptive label to be used if an error is raised
- **li** (*list*) – List of object references (which may include `None`)

Raises **ValueMismatchError** – if references differ

Returns the object or `None`

device_address (*string*)

Parser helper function for device address arguments.

Validate string is an appropriately formed device address such as `'1:0'`.

Parameters `string` (*str*) – String to validate

Raises `InvalidInputError` – if string is not a well-formatted device address

Returns Validated string (with leading/trailing whitespace stripped)

mac_address (*string*)

Parser helper function for MAC address arguments.

Validate whether a string is a valid MAC address. Recognized formats are:

- `XX:XX:XX:XX:XX:XX`

- `XX-XX-XX-XX-XX-XX`

- `XXXX.XXXX.XXXX`

Parameters `string` – String to validate

Raises `InvalidInputError` – if string is not a valid MAC address

Returns Validated string (with leading/trailing whitespace stripped)

match_or_die (*first_label*, *first*, *second_label*, *second*)

Make sure “first” and “second” are equal or raise an error.

Parameters

- **first_label** (*str*) – Descriptive label for *first*
- **first** – First object to compare
- **second_label** (*str*) – Descriptive label for *second*
- **second** – Second object to compare

Raises `ValueMismatchError` – if *first* != *second*

natural_sort (*l*)

Sort the given list “naturally” rather than in ASCII order.

E.g, “10” comes after “9” rather than between “1” and “2”.

See also http://nedbatchelder.com/blog/200712/human_sorting.html

Parameters `l` (*list*) – List to sort

Returns Sorted list

no_whitespace (*string*)

Parser helper function for arguments not allowed to contain whitespace.

Parameters `string` (*str*) – String to validate

Raises `InvalidInputError` – if string contains internal whitespace

Returns Validated string (with leading/trailing whitespace stripped)

non_negative_int (*string*)

Parser helper function for integer arguments that must be 0 or more.

Alias for `validate_int()` setting minimum to 0.

positive_int (*string*)

Parser helper function for integer arguments that must be 1 or more.

Alias for `validate_int()` setting minimum to 1.

to_string (*obj*)

Get string representation of an object, special-case for XML Element.

truth_value (*value*)

Parser helper function for truth values like '0', 'y', or 'false'.

validate_int (*string*, *minimum=None*, *maximum=None*, *label='input'*)

Parser helper function for validating integer arguments in a range.

Parameters

- **string** (*str*) – String to convert to an integer and validate
- **minimum** (*int*) – Minimum valid value (optional)
- **maximum** (*int*) – Maximum valid value (optional)
- **label** (*str*) – Label to include in any errors raised

Returns Validated integer value

Raises

- **ValueUnsupportedError** – if *string* can't be converted to int
- **ValueTooLowError** – if value is less than *minimum*
- **ValueTooHighError** – if value is more than *maximum*

NIC_TYPES = ['E1000e', 'E1000', 'PCNet32', 'virtio', 'VMXNET3']

List of NIC type strings recognized as canonical.

7.3.2 COT.file_reference module

Wrapper classes to abstract away differences between file sources.

class FileInTAR (*tarfile_path*, *filename*)

Bases: object

Wrapper for a file inside a TAR archive or OVA.

add_to_archive (*tarf*)

Copy this file into the given tarfile object.

close ()

Close the file object previously opened.

copy_to (*dest_dir*)

Extract this file to the given destination directory.

exists ()

Check whether the file exists in the TAR archive.

open (*mode*)

Open the TAR and return a reference to the relevant file object.

size ()

Get the size of this file in bytes.

class FileOnDisk (*file_path*, *filename=None*)

Bases: object

Wrapper for a 'real' file on disk.

add_to_archive (*tarf*)
Copy this file into the given tarfile object.

close ()
Close the file previously opened.

copy_to (*dest_dir*)
Copy this file to the given destination directory.

exists ()
Check whether the file exists on disk.

open (*mode*)
Open the file and return a reference to the file object.

size ()
Get the size of this file, in bytes.

7.3.3 COT.platforms module

Handles behavior that varies between guest platforms.

Functions

<code>platform_from_product_class</code>	Get the class of Platform corresponding to a product class string.
--	--

Classes

<i>GenericPlatform</i>	Generic class for operations that depend on guest platform.
<i>CSR1000V</i>	Platform-specific logic for Cisco CSR1000V platform.
<i>IOSv</i>	Platform-specific logic for Cisco IOSv.
<i>IOSXRv</i>	Platform-specific logic for Cisco IOS XRv platform.
<i>IOSXRvRP</i>	Platform-specific logic for Cisco IOS XRv HA-capable RP.
<i>IOSXRvLC</i>	Platform-specific logic for Cisco IOS XRv line card.
<i>IOSXRv9000</i>	Platform-specific logic for Cisco IOS XRv 9000 platform.
<i>NXOSv</i>	Platform-specific logic for Cisco NX-OSv (Titanium).

Constants

<code>PRODUCT_PLATFORM_MAP</code>	Mapping of known product class strings to Platform classes.
-----------------------------------	---

class **GenericPlatform**

Bases: object

Generic class for operations that depend on guest platform.

To be used whenever the guest is unrecognized or does not need special handling.

classmethod **controller_type_for_device** (*_device_type*)

Get the default controller type for the given device type.

classmethod **guess_nic_name** (*nic_number*)

Guess the name of the Nth NIC for this platform.

Note: This method counts from 1, not from 0!

classmethod validate_cpu_count (*cpus*)

Throw an error if the number of CPUs is not a supported value.

classmethod validate_memory_amount (*mebibytes*)

Throw an error if the amount of RAM is not supported.

classmethod validate_nic_count (*count*)

Throw an error if the number of NICs is not supported.

classmethod validate_nic_type (*type_string*)

Throw an error if the NIC type string is not supported.

See also:

- `COT.data_validation.canonicalize_nic_subtype()`
- `COT.data_validation.NIC_TYPES`

classmethod validate_nic_types (*type_list*)

Throw an error if any NIC type string in the list is unsupported.

classmethod validate_serial_count (*count*)

Throw an error if the number of serial ports is not supported.

BOOTSTRAP_DISK_TYPE = 'cdrom'

CONFIG_TEXT_FILE = 'config.txt'

LITERAL_CLI_STRING = 'config'

PLATFORM_NAME = '(unrecognized platform, generic)'

SECONDARY_CONFIG_TEXT_FILE = None

SUPPORTED_NIC_TYPES = ['E1000e', 'E1000', 'PCNet32', 'virtio', 'VMXNET3']

class CSR1000V

Bases: `COT.platforms.GenericPlatform`

Platform-specific logic for Cisco CSR1000V platform.

classmethod controller_type_for_device (*device_type*)

CSR1000V uses SCSI for hard disks and IDE for CD-ROMs.

classmethod guess_nic_name (*nic_number*)

GigabitEthernet1, GigabitEthernet2, etc.

Warning: In all current CSR releases, NIC names start at “GigabitEthernet1”. Some early versions started at “GigabitEthernet0” but we don’t support that.

classmethod validate_cpu_count (*cpus*)

CSR1000V supports 1, 2, or 4 CPUs.

classmethod validate_memory_amount (*mebibytes*)

Minimum 2.5 GiB, max 8 GiB.

classmethod validate_nic_count (*count*)

CSR1000V requires 3 NICs and supports up to 26.

classmethod validate_serial_count (*count*)

CSR1000V supports 0-2 serial ports.

CONFIG_TEXT_FILE = 'iosxe_config.txt'

```

LITERAL_CLI_STRING = 'ios-config'
PLATFORM_NAME = 'Cisco CSR1000V'
SUPPORTED_NIC_TYPES = ['E1000', 'virtio', 'VMXNET3']

```

class IOSv

Bases: *COT.platforms.GenericPlatform*

Platform-specific logic for Cisco IOSv.

classmethod guess_nic_name (*nic_number*)
GigabitEthernet0/0, GigabitEthernet0/1, etc.

classmethod validate_cpu_count (*cpus*)
IOSv only supports a single CPU.

classmethod validate_memory_amount (*mebibytes*)
IOSv has minimum 192 MiB (with minimal feature set), max 3 GiB.

classmethod validate_nic_count (*count*)
IOSv supports up to 16 NICs.

classmethod validate_serial_count (*count*)
IOSv requires 1-2 serial ports.

BOOTSTRAP_DISK_TYPE = 'harddisk'

CONFIG_TEXT_FILE = 'ios_config.txt'

LITERAL_CLI_STRING = None

PLATFORM_NAME = 'Cisco IOSv'

SUPPORTED_NIC_TYPES = ['E1000']

class IOSXRv

Bases: *COT.platforms.GenericPlatform*

Platform-specific logic for Cisco IOS XRv platform.

classmethod guess_nic_name (*nic_number*)
MgmtEth0/0/CPU0/0, GigabitEthernet0/0/0/0, Gig0/0/0/1, etc.

classmethod validate_cpu_count (*cpus*)
IOS XRv supports 1-8 CPUs.

classmethod validate_memory_amount (*mebibytes*)
Minimum 3 GiB, max 8 GiB of RAM.

classmethod validate_nic_count (*count*)
IOS XRv requires at least one NIC.

classmethod validate_serial_count (*count*)
IOS XRv supports 1-4 serial ports.

CONFIG_TEXT_FILE = 'iosxr_config.txt'

LITERAL_CLI_STRING = None

PLATFORM_NAME = 'Cisco IOS XRv'

SECONDARY_CONFIG_TEXT_FILE = 'iosxr_config_admin.txt'

SUPPORTED_NIC_TYPES = ['E1000', 'virtio']

class IOSXRvRPBases: *COT.platforms.IOSXRv*

Platform-specific logic for Cisco IOS XRv HA-capable RP.

classmethod guess_nic_name (*nic_number*)

Fabric and management only.

- fabric
- MgmtEth0/{SLOT}/CPU0/0

classmethod validate_nic_count (*count*)

Fabric plus an optional management NIC.

PLATFORM_NAME = 'Cisco IOS XRv route processor card'**class IOSXRvLC**Bases: *COT.platforms.IOSXRv*

Platform-specific logic for Cisco IOS XRv line card.

classmethod guess_nic_name (*nic_number*)

Fabric interface plus slot-appropriate GigabitEthernet interfaces.

- fabric
- GigabitEthernet0/{SLOT}/0/0
- GigabitEthernet0/{SLOT}/0/1
- etc.

classmethod validate_serial_count (*count*)

No serial ports are needed but up to 4 can be used for debugging.

CONFIG_TEXT_FILE = None**PLATFORM_NAME** = 'Cisco IOS XRv line card'**SECONDARY_CONFIG_TEXT_FILE** = None**class NXOSv**Bases: *COT.platforms.GenericPlatform*

Platform-specific logic for Cisco NX-OSv (Titanium).

classmethod guess_nic_name (*nic_number*)

NX-OSv names its NICs a bit interestingly...

- mgmt0
- Ethernet2/1
- Ethernet2/2
- ...
- Ethernet2/48
- Ethernet3/1
- Ethernet3/2
- ...

classmethod validate_cpu_count (*cpus*)

NX-OSv requires 1-8 CPUs.

classmethod validate_memory_amount (*mebibytes*)

NX-OSv requires 2-8 GiB of RAM.

classmethod validate_serial_count (*count*)

NX-OSv requires 1-2 serial ports.

CONFIG_TEXT_FILE = 'nxos_config.txt'

LITERAL_CLI_STRING = None

PLATFORM_NAME = 'Cisco NX-OSv'

SUPPORTED_NIC_TYPES = ['E1000', 'virtio']

7.4 User interface modules

<code>COT.ui_shared</code>	Abstract user interface superclass.
<code>COT.cli</code>	CLI entry point for the Common OVF Tool (COT) suite.

7.4.1 COT.ui_shared module

Abstract user interface superclass.

class UI (*force=False*)

Bases: object

Abstract user interface functionality.

Can also be used in test code as a stub that autoconfirms everything.

choose_from_list (*footer, option_list, default_value, header='', info_list=None*)

Prompt the user to choose from a list.

Parameters

- **footer** – Prompt string to display following the list
- **option_list** – List of strings to choose amongst
- **default_value** – Default value to select if user declines
- **header** – String to display prior to the list
- **info_list** – Verbose strings to display instead of option_list

confirm (*prompt*)

Prompt user to confirm the requested operation.

Auto-accepts if *force* is set to True.

Warning: This stub implementation does not actually interact with the user, but instead returns `default_confirm_response`. Subclasses should override this method.

Parameters **prompt** (*str*) – Message to prompt the user with

Returns True (user confirms acceptance) or False (user declines)

confirm_or_die (*prompt*)

If the user doesn't agree, abort the program.

A simple wrapper for `confirm()` that calls `sys.exit()` if `confirm()` returns False.

fill_examples (*example_list*)

Pretty-print a set of usage examples.

Parameters **example_list** (*list*) – List of (example, description) tuples.

Raises **NotImplementedError** – Must be implemented by a subclass.

fill_usage (*subcommand, usage_list*)

Pretty-print a list of usage strings.

Parameters

- **subcommand** (*str*) – Subcommand name/keyword
- **usage_list** (*list*) – List of usage strings for this subcommand.

Returns String containing all usage strings, each appropriately wrapped to the *terminal_width* value.

get_input (*prompt, default_value*)

Prompt the user to enter a string.

Auto-inputs the *default_value* if *force* is set to True.

Warning: This stub implementation does not actually interact with the user, but instead always returns *default_value*. Subclasses should override this method.

Parameters

- **prompt** (*str*) – Message to prompt the user with
- **default_value** (*str*) – Default value to input if the user simply hits Enter without entering a value, or if *force*.

Returns Input value

Return type str

get_password (*username, host*)

Get password string from the user.

Parameters

- **username** (*str*) – Username the password is associated with
- **host** (*str*) – Host the password is associated with

Raises **NotImplementedError** – Must be implemented by a subclass.

default_confirm_response = None

Knob for API testing, sets the default response to confirm().

force = None

Whether to automatically select the default value in all cases.

(As opposed to interactively prompting the user.)

terminal_width

Get the width of the terminal in columns.

7.4.2 COT.cli module

CLI entry point for the Common OVF Tool (COT) suite.

Functions

formatter Create formatter for log output.

Classes

CLI Command-line user interface for COT.

class CLI (*terminal_width=None*)

Bases: *COT.ui_shared.UI*

Command-line user interface for COT.

<i>confirm</i>	Prompt user to confirm the requested operation.
<i>create_parser</i>	Create parser object for global cot command.
<i>create_subparsers</i>	Populate the CLI sub-parsers for all known submodules.
<i>fill_examples</i>	Pretty-print a set of usage examples.
<i>fill_usage</i>	Pretty-print a list of usage strings for a COT subcommand.
<i>get_input</i>	Prompt the user to enter a string.
<i>get_password</i>	Get password string from the user.
<i>main</i>	Main worker function for COT when invoked from the CLI.
<i>parse_args</i>	Parse the given CLI arguments into a namespace object.
<i>run</i>	Parse the given CLI args then run.
<i>set_verbosity</i>	Enable logging and/or change the logging verbosity level.
<i>terminal_width</i>	The width of the terminal in columns.

add_subparser (*title*, *parent=None*, *aliases=None*, *lookup_prefix=''*, ***kwargs*)

Create a subparser under the specified parent.

Parameters

- **title** (*str*) – Canonical keyword for this subparser
- **parent** (*object*) – Subparser grouping object returned by `ArgumentParser.add_subparsers()`
- **aliases** (*list*) – Aliases for `title`. Only used in Python 3.x.
- **lookup_prefix** (*str*) – String to prepend to `title` and each alias in `aliases` for lookup purposes.

static args_to_dict (*args*)

Convert args to a dict and perform any needed cleanup.

confirm (*prompt*)

Prompt user to confirm the requested operation.

Auto-accepts if `force` is set to `True`.

Parameters **prompt** (*str*) – Message to prompt the user with

Returns `True` (user confirms acceptance) or `False` (user declines)

create_parser ()

Create parser object for global cot command.

Includes a number of globally applicable CLI options.

create_subparsers ()

Populate the CLI sub-parsers for all known submodules.

Creates an instance of each *COTGenericSubmodule* subclass, then calls *create_subparser()* for each.

fill_examples (*example_list*)

Pretty-print a set of usage examples.

```
>>> print(CLI(70).fill_examples([
...     ("Deploy to vSphere/ESXi server 192.0.2.100 with credentials"
...      " admin/admin, creating a VM named 'test_vm' from foo.ova.",
...      'cot deploy foo.ova esxi 192.0.2.100 -u admin -p admin'
...      ' -n test_vm'),
...     ("Deploy to vSphere/ESXi server 192.0.2.100, with username"
...      " admin (prompting the user to input a password at runtime)",
...      " creating a VM based on profile '1CPU-2.5GB' in foo.ova.",
...      'cot deploy foo.ova esxi 192.0.2.100 -u admin -c 1CPU-2.5GB')
... ]))
```

Examples:

```
Deploy to vSphere/ESXi server 192.0.2.100 with credentials
admin/admin, creating a VM named 'test_vm' from foo.ova.
```

```
    cot deploy foo.ova esxi 192.0.2.100 -u admin -p admin \
        -n test_vm
```

```
Deploy to vSphere/ESXi server 192.0.2.100, with username admin
(prompting the user to input a password at runtime), creating a VM
based on profile '1CPU-2.5GB' in foo.ova.
```

```
    cot deploy foo.ova esxi 192.0.2.100 -u admin -c 1CPU-2.5GB
```

Parameters **example_list** (*list*) – List of (description, CLI example) tuples.

Returns Examples wrapped appropriately to the *terminal_width()* value. CLI examples will be wrapped with backslashes and a hanging indent.

fill_usage (*subcommand*, *usage_list*)

Pretty-print a list of usage strings for a COT subcommand.

Automatically prepends a `cot subcommand --help` usage string to the provided list.

```
>>> print(CLI(50).fill_usage('add-file',
...     ["FILE PACKAGE [-o OUTPUT] [-f FILE_ID]"]))

cot add-file --help
cot <opts> add-file FILE PACKAGE [-o OUTPUT]
                        [-f FILE_ID]
```

Parameters

- **subcommand** (*str*) – Subcommand name/keyword
- **usage_list** (*list*) – List of usage strings for this subcommand.

Returns String containing all usage strings, each appropriately wrapped to the *terminal_width()* value.

get_input (*prompt*, *default_value*)

Prompt the user to enter a string.

Auto-inputs the *default_value* if *force* is set to *True*.

Parameters

- **prompt** (*str*) – Message to prompt the user with
- **default_value** (*str*) – Default value to input if the user simply hits Enter without entering a value, or if *force*.

Returns Input value

Return type *str*

get_password (*username*, *host*)

Get password string from the user.

Parameters

- **username** (*str*) – Username the password is associated with
- **host** (*str*) – Host the password is associated with

Raises **InvalidInputError** – if *force* is *True* (as there is no “default” password value)

main (*args*)

Main worker function for COT when invoked from the CLI.

- Calls *set_verbosity()* with the appropriate verbosity level derived from the args.
- Looks up the appropriate *COTGenericSubmodule* instance corresponding to the subcommand that was invoked.
- Converts *args* to a dict and calls *set_value()* for each arg/value in the dict.
- Calls *run()* followed by *finished()*.
- Catches various exceptions and handles them appropriately.

Parameters **args** – Parser namespace object returned from *parse_args()*.

Return type *int*

Returns

Exit code for the COT executable.

- 0 on successful completion
- 1 on runtime error
- 2 on input error (parser error, *InvalidInputError*, etc.)

parse_args (*argv*)

Parse the given CLI arguments into a namespace object.

Parameters **argv** (*list*) – List of CLI arguments, not including *argv0*

Returns Parser namespace object

run (*argv*)

Parse the given CLI args then run.

Calls *parse_args()* followed by *main()*.

Parameters **argv** (*list*) – The CLI argv value (not including *argv[0]*)

Returns Return code from *main()*

static set_instance_attributes (*arg_dict*)

Pass the CLI argument dictionary to the instance attributes TODO.

Raises `InvalidInputError` – if attributes are not validly set.

`set_verbosity (level)`

Enable logging and/or change the logging verbosity level.

Will call `formatter()` and associate the resulting formatter with logging.

Parameters `level` – Logging level as defined by logging

`terminal_width`

The width of the terminal in columns.

`formatter (verbosity=20)`

Create formatter for log output.

We offer different (more verbose) formatting when debugging is enabled, hence this need.

Parameters `verbosity` – Logging level as defined by logging.

Returns Formatter object for use with logging.

Return type instance of `colorlog.ColoredFormatter`

`main ()`

Launch COT from the CLI.

7.5 Sub-packages

<code>COT.helpers</code>	Provide various non-Python helper programs that COT makes use of.
<code>COT.ovf</code>	Package for handling OVF and OVA virtual machine description files.

7.5.1 `COT.helpers` package reference

Provide various non-Python helper programs that COT makes use of.

In general, COT submodules should work through the APIs provided in `COT.helpers.api` rather than accessing individual helper program classes. This gives us the flexibility to change the specific set of helper programs that are used to provide any given functionality with minimal impact to COT as a whole.

API

<code>convert_disk_image</code>	Convert the given disk image to the requested format/subformat.
<code>create_disk_image</code>	Create a new disk image at the requested location.
<code>get_checksum</code>	Get the checksum of the given file.
<code>get_disk_capacity</code>	Get the storage capacity of the given disk image.
<code>get_disk_format</code>	Get the disk image format of the given file.
<code>install_file</code>	Copy the given src to the given dest, using sudo if needed.
<code>create_install_dir</code>	Check whether the given target directory exists, and create if not.
<code>download_and_expand</code>	Context manager for downloading and expanding a .tar.gz file.

Exceptions

<i>HelperError</i>	A helper program exited with non-zero return code.
<i>HelperNotFoundError</i>	A helper program cannot be located.

Helper modules

<i>COT.helpers.api</i>	API for abstract access to third-party helper tools.
<i>COT.helpers.helper</i>	Interface for providers of non-Python helper programs.
<i>COT.helpers.fatdisk</i>	Give COT access to <code>fatdisk</code> for creating and updating FAT32 file systems.
<i>COT.helpers.mkisofs</i>	Give COT access to <code>mkisofs</code> , <code>genisoimage</code> , or <code>xorriso</code> for creating ISO images.
<i>COT.helpers.ovftool</i>	Give COT access to <code>ovftool</code> for validating and deploying OVF to ESXi.
<i>COT.helpers.qemu_img</i>	Give COT access to <code>qemu-img</code> for manipulating disk image formats.
<i>COT.helpers.vmdktool</i>	Give COT access to <code>vmdktool</code> for manipulating compressed VMDK files.

COT.helpers.api module

API for abstract access to third-party helper tools.

Abstracts away operations that require third-party helper programs, especially those that are not available through PyPI.

The actual helper programs are provided by individual classes in this package.

Functions

<i>convert_disk_image</i>	Convert the given disk image to the requested format/subformat.
<i>create_disk_image</i>	Create a new disk image at the requested location.
<i>create_install_dir</i>	Check whether the given target directory exists, and create if not.
<i>download_and_expand</i>	Context manager for downloading and expanding a .tar.gz file.
<i>get_checksum</i>	Get the checksum of the given file.
<i>get_disk_capacity</i>	Get the storage capacity of the given disk image.
<i>get_disk_format</i>	Get the disk image format of the given file.
<i>install_file</i>	Copy the given src to the given dest, using sudo if needed.

convert_disk_image (*file_path*, *output_dir*, *new_format*, *new_subformat=None*)

Convert the given disk image to the requested format/subformat.

If the disk is already in this format then it is unchanged; otherwise, will convert to a new disk in the specified *output_dir* and return its path.

Current supported conversions:

- .vmdk (any format) to .vmdk (streamOptimized)
- .img to .vmdk (streamOptimized)

Parameters

- **file_path** (*str*) – Disk image file to inspect/convert
- **output_dir** (*str*) – Directory to place converted image into, if needed
- **new_format** (*str*) – Desired final format
- **new_subformat** (*str*) – Desired final subformat

Returns

- `file_path`, if no conversion was required
- or a file path in `output_dir` containing the converted image

Raises **ValueUnsupportedError** – if the `new_format` and/or `new_subformat` are not supported conversion targets.

create_disk_image (*file_path*, *file_format=None*, *capacity=None*, *contents=None*)

Create a new disk image at the requested location.

Either `capacity` or `contents` or both must be specified.

Parameters

- **file_path** (*str*) – Desired location of new disk image
- **file_format** (*str*) – Desired image format (if not specified, this will be derived from the file extension of `file_path`)
- **capacity** – Disk capacity. A string like ‘16M’ or ‘1G’.
- **contents** (*list*) – List of file paths to package into the created image. If not specified, the image will be left blank and unformatted.

create_install_dir (*directory*, *permissions=493*)

Check whether the given target directory exists, and create if not.

Parameters

- **directory** (*str*) – Directory to check/create.
- **permissions** (*int*) – Permissions bits to set on the directory.

Returns True

download_and_expand (**args*, ***kws*)

Context manager for downloading and expanding a .tar.gz file.

Creates a temporary directory, downloads the specified URL into the directory, unzips and untars the file into this directory, then yields to the given block. When the block exits, the temporary directory and its contents are deleted.

```
with download_and_expand("http://example.com/foo.tgz") as d:
    # archive contents have been extracted to 'd'
    ...
# d is automatically cleaned up.
```

Parameters **url** (*str*) – URL of a .tgz or .tar.gz file to download.

get_checksum (*path_or_obj*, *checksum_type*)

Get the checksum of the given file.

Parameters

- **path_or_obj** (*str*) – File path to checksum OR an opened file object
- **checksum_type** (*str*) – Supported values are ‘md5’ and ‘sha1’.

Returns String containing hexadecimal file checksum

get_disk_capacity (*file_path*)

Get the storage capacity of the given disk image.

Parameters **file_path** (*str*) – Path to disk image file to inspect

Returns Disk capacity, in bytes

get_disk_format (*file_path*)

Get the disk image format of the given file.

Warning: If *file_path* refers to a file which is not a disk image at all, this function will return ('raw', None).

Parameters *file_path* (*str*) – Path to disk image file to inspect.

Returns

(format, subformat)

- format may be 'vmdk', 'raw', or 'qcow2'
- subformat may be None, or various strings for 'vmdk' files.

install_file (*src*, *dest*)

Copy the given src to the given dest, using sudo if needed.

Parameters

- **src** (*str*) – Source path.
- **dest** (*str*) – Destination path.

Returns True

COT.helpers.helper module

Interface for providers of non-Python helper programs.

Provides the ability to install the program if not already present, and the ability to run the program as well.

exception HelperError

Bases: `exceptions.EnvironmentError`

A helper program exited with non-zero return code.

exception HelperNotFoundError

Bases: `exceptions.OSError`

A helper program cannot be located.

class Helper (*name*, *version_args*=None, *version_regexp*='([0-9.]+'')

Bases: `object`

A provider of a non-Python helper program.

Class Properties

<code>PACKAGE MANAGERS</code>	Class-level lookup for package manager executables.
-------------------------------	---

Class Methods

<code>confirm</code>	Prompt user to confirm the requested operation.
<code>apt_install</code>	Try to use apt-get to install a package.
<code>port_install</code>	Try to use port to install a package.
<code>yum_install</code>	Try to use yum to install a package.
<code>find_executable</code>	Wrapper for <code>distutils.spawn.find_executable()</code> .

Continued on next page

Table 7.34 – continued from previous page

<code>make_install_dir</code>	Check whether the given target directory exists, and create if not.
<code>install_file</code>	Copy the given src to the given dest, using sudo if needed.

Instance Properties

<code>name</code>	Name of the helper program.
<code>path</code>	Discovered path to the helper.
<code>version</code>	Release version of the associated helper program.

Instance Methods

<code>call_helper</code>	Call the helper program with the given arguments.
<code>install_helper</code>	Install the helper program (abstract method).

`__init__` (*name*, *version_args=None*, *version_regex='([0-9.]+)'*)
Initializer.

Parameters

- **name** – Name of helper executable
- **version_args** (*list*) – Args to pass to the helper to get its version. Defaults to `['--version']` if unset.
- **version_regex** – Regexp to get the version number from the output of the command.

classmethod `apt_install` (*package*)
Try to use `apt-get` to install a package.

call_helper (*args*, *capture_output=True*, *require_success=True*)
Call the helper program with the given arguments.

Parameters

- **args** (*list*) – List of arguments to the helper program.
- **capture_output** (*boolean*) – If `True`, `stdout/stderr` will be redirected to a buffer and returned, instead of being displayed to the user.
- **require_success** (*boolean*) – if `True`, an exception will be raised if the helper exits with a non-zero status code.

Returns Captured `stdout/stderr` (if `capture_output`), else `None`.

static `find_executable` (*name*)
Wrapper for `distutils.spawn.find_executable()`.

classmethod `install_file` (*src*, *dest*)
Copy the given `src` to the given `dest`, using `sudo` if needed.

Parameters

- **src** (*str*) – Source path.
- **dest** (*str*) – Destination path.

Returns `True`

install_helper ()
Install the helper program (abstract method).

Raise `NotImplementedError` as this method must be implemented by a concrete subclass.

classmethod `make_install_dir(directory, permissions=493)`

Check whether the given target directory exists, and create if not.

Parameters `directory` – Directory to check/create.

classmethod `port_install(package)`

Try to use `port` to install a package.

should_not_be_installed_but_is()

Check whether the tool is already installed.

Returns `False`, and logs a warning message, if installed

Returns `True`, if not installed

classmethod `yum_install(package)`

Try to use `yum` to install a package.

PACKAGE MANAGERS = {'apt-get': '/usr/bin/apt-get', 'yum': None, 'port': None}

Class-level lookup for package manager executables.

name

Name of the helper program.

path

Discovered path to the helper.

version

Release version of the associated helper program.

guess_file_format_from_path(file_path)

Guess the preferred file format based on file path/extension.

`COT.helpers.fatdisk` module

Give COT access to `fatdisk` for creating and updating FAT32 file systems.

<http://github.com/goblinhack/fatdisk>

class `FatDisk`

Bases: `COT.helpers.helper.Helper`

Helper provider for `fatdisk` (<http://github.com/goblinhack/fatdisk>).

Methods

<code>install_helper</code>	Install <code>fatdisk</code> .
<code>create_raw_image</code>	Create a new FAT32-formatted raw image at the requested location.

create_raw_image(file_path, contents, capacity=None)

Create a new FAT32-formatted raw image at the requested location.

Parameters

- **file_path** (*str*) – Desired location of new disk image
- **contents** (*list*) – List of file paths to package into the created image.
- **capacity** – (optional) Disk capacity. A string like '16M' or '1G'.

```
install_helper()  
    Install fatdisk.
```

`COT.helpers.mkisofs` module

Give COT access to mkisofs, genisoimage, or xorriso for creating ISO images.

<http://cdrecord.org/> <https://www.gnu.org/software/xorriso/>

class `MkIsoFS`

Bases: `COT.helpers.helper.Helper`

Helper provider for mkisofs, genisoimage, or xorriso.

<http://cdrecord.org/> <https://www.gnu.org/software/xorriso/>

Methods

<code>install_helper</code>	Install mkisofs, genisoimage, or xorriso.
<code>create_iso</code>	Create a new ISO image at the requested location.

```
create_iso(file_path, contents)
```

Create a new ISO image at the requested location.

Parameters

- **file_path** (*str*) – Desired location of new disk image
- **contents** (*list*) – List of file paths to package into the created image.

```
install_helper()
```

Install mkisofs, genisoimage, or xorriso.

name

Either mkisofs, genisoimage, or xorriso depending on environment.

path

Find mkisofs, genisoimage, or xorriso if available.

`COT.helpers.ovftool` module

Give COT access to ovftool for validating and deploying OVF to ESXi.

<https://www.vmware.com/support/developer/ovf/>

class `OVFTool`

Bases: `COT.helpers.helper.Helper`

Helper provider for ovftool from VMware.

<https://www.vmware.com/support/developer/ovf/>

Methods

<code>install_helper</code>	Install ovftool.
<code>validate_ovf</code>	Use VMware's ovftool program to validate an OVF or OVA.

```
install_helper()
```

Install ovftool.

Raise `NotImplementedError` as VMware does not currently provide any mechanism for automatic download of ovftool.

validate_ovf (*ovf_file*)

Use VMware's ovftool program to validate an OVF or OVA.

This checks the file against the OVF standard and any VMware-specific requirements.

Parameters **ovf_file** (*str*) – File to validate

Returns Output from ovftool

Raises

- **HelperNotFoundError** – if ovftool is not found.
- **HelperError** – if ovftool regards the file as invalid

`COT.helpers.qemu_img` module

Give COT access to qemu-img for manipulating disk image formats.

<http://www.qemu.org>

class **QEMUImg**

Bases: `COT.helpers.helper.Helper`

Helper provider for qemu-img (<http://www.qemu.org>).

Methods

<code>install_helper</code>	Install qemu-img.
<code>get_disk_format</code>	Get the major disk image format of the given file.
<code>get_disk_capacity</code>	Get the storage capacity of the given disk image.
<code>convert_disk_image</code>	Convert the given disk image to the requested format/subformat.
<code>create_blank_disk</code>	Create an unformatted disk image at the requested location.

convert_disk_image (*file_path*, *output_dir*, *new_format*, *new_subformat=None*)

Convert the given disk image to the requested format/subformat.

If the disk is already in this format then it is unchanged; otherwise, will convert to a new disk in the specified output_dir and return its path.

Current supported conversions:

- .vmdk (any format) to .vmdk (streamOptimized)
- .img to .vmdk (streamOptimized)

Parameters

- **file_path** (*str*) – Disk image file to inspect/convert
- **output_dir** (*str*) – Directory to place converted image into, if needed
- **new_format** (*str*) – Desired final format
- **new_subformat** (*str*) – Desired final subformat

Returns

- *file_path*, if no conversion was required

- or a file path in `output_dir` containing the converted image

Raises `NotImplementedError` – if the `new_format` and/or `new_subformat` are not supported conversion targets.

`create_blank_disk` (*file_path*, *capacity*, *file_format=None*)

Create an unformatted disk image at the requested location.

Parameters

- **`file_path`** (*str*) – Desired location of new disk image
- **`capacity`** – Disk capacity. A string like ‘16M’ or ‘1G’.
- **`file_format`** (*str*) – Desired image format (if not specified, this will be derived from the file extension of `file_path`)

`get_disk_capacity` (*file_path*)

Get the storage capacity of the given disk image.

Parameters **`file_path`** (*str*) – Path to disk image file to inspect

Returns Disk capacity, in bytes

`get_disk_format` (*file_path*)

Get the major disk image format of the given file.

Warning: If `file_path` refers to a file which is not a disk image at all, this function will return ‘raw’.

Parameters **`file_path`** (*str*) – Path to disk image file to inspect.

Returns Disk image format (‘vmdk’, ‘raw’, ‘qcow2’, etc.)

`install_helper` ()

Install `qemu-img`.

`COT.helpers.vmdktool` module

Give COT access to `vmdktool` for manipulating compressed VMDK files.

<http://www.freshports.org/sysutils/vmdktool/>

class `VmdkTool`

Bases: `COT.helpers.helper.Helper`

Helper provider for `vmdktool`.

<http://www.freshports.org/sysutils/vmdktool/>

Methods

<code>install_helper</code>	Install <code>vmdktool</code> .
<code>convert_disk_image</code>	Convert the given disk image to the requested format/subformat.

`convert_disk_image` (*file_path*, *output_dir*, *new_format*, *new_subformat=None*)

Convert the given disk image to the requested format/subformat.

If the disk is already in this format then it is unchanged; otherwise, will convert to a new disk in the specified `output_dir` and return its path.

Current supported conversions:

- `.vmdk` (any format) to `.vmdk` (streamOptimized)
- `.img` to `.vmdk` (streamOptimized)

Parameters

- **file_path** (*str*) – Disk image file to inspect/convert
- **output_dir** (*str*) – Directory to place converted image into, if needed
- **new_format** (*str*) – Desired final format
- **new_subformat** (*str*) – Desired final subformat

Returns

- `file_path`, if no conversion was required
- or a file path in `output_dir` containing the converted image

Raises **NotImplementedError** – if the `new_format` and/or `new_subformat` are not supported conversion targets.

```
install_helper()
    Install vmdktool.
```

7.5.2 COT.ovf package reference

Package for handling OVF and OVA virtual machine description files.

The `COT.ovf.OVF` class provides an implementation of the `COT.vm_description.VMDescription` interface. In general, COT submodules should be agnostic of the internals of this package and should only use the `VMDescription` interface.

API

<i>OVF</i>	Representation of the contents of an OVF or OVA.
------------	--

Exceptions

<i>OVFHardwareDataError</i>	The input data used to construct an <code>OVFHardware</code> is not sane.
<i>OVFItemDataError</i>	Data to be added to an <code>OVFItem</code> conflicts with existing data.

Modules

<i>COT.ovf.ovf</i>	Module for handling OVF and OVA virtual machine description files.
<i>COT.ovf.hardware</i>	Representation of OVF hardware definitions.
<i>COT.ovf.item</i>	Module for working with individual hardware elements in an OVF.
<i>COT.ovf.name_helper</i>	Module for handling the differences in XML between OVF spec versions.

COT.ovf.ovf module

Module for handling OVF and OVA virtual machine description files.

Functions

<code>byte_count</code>	Convert an OVF-style value + multiplier into decimal byte count.
<code>byte_string</code>	Pretty-print the given bytes value.
<code>factor_bytes</code>	Convert a byte count into OVF-style bytes + multiplier.

Classes

<code>OVF</code>	Representation of the contents of an OVF or OVA.
------------------	--

class `OVF` (*input_file*, *output_file*)

Bases: `COT.vm_description.VMDescription`, `COT.xml_file.XML`

Representation of the contents of an OVF or OVA.

Properties

<code>input_file</code>	Data file to read in.
<code>output_file</code>	OVF or OVA file that will be created or updated by <code>write()</code> .
<code>ovf_version</code>	Float representing the OVF specification version in use.
<code>product_class</code>	The product class identifier, such as <code>com.cisco.csr1000v</code> .
<code>platform</code>	The platform type, as determined from the OVF descriptor.
<code>config_profiles</code>	The list of supported configuration profiles.
<code>default_config_profile</code>	The name of the default configuration profile.
<code>environment_properties</code>	The array of environment properties.
<code>environment_transports</code>	The list of environment transport methods.
<code>networks</code>	The list of network names currently defined in this VM.
<code>network_descriptions</code>	The list of network descriptions currently defined in this VM.
<code>system_types</code>	List of virtual system type(s) supported by this virtual machine.
<code>version_short</code>	Short descriptive version string (XML <code>Version</code> element).
<code>version_long</code>	Long descriptive version string (XML <code>FullVersion</code> element).

add_controller_device (*device_type*, *subtype*, *address*, *ctrl_item=None*)

Create a new IDE or SCSI controller, or update existing one.

Parameters

- **device_type** (*str*) – ‘ide’ or ‘scsi’
- **subtype** – Subtype such as ‘virtio’ (optional), or list of subtype values
- **address** (*int*) – Controller address such as 0 or 1 (optional)
- **ctrl_item** (`OVFItem`) – Existing controller device to update (optional)

Returns New or updated controller device object

add_disk (*file_path*, *file_id*, *disk_type*, *disk=None*)

Add a new disk object to the VM or overwrite the provided one.

Parameters

- **file_path** (*str*) – Path to disk image file
- **file_id** (*str*) – Identifier string for the file/disk mapping
- **disk_type** (*str*) – ‘harddisk’ or ‘cdrom’

- **disk** (*xml.etree.ElementTree.Element*) – Existing disk object to overwrite

Returns New or updated disk object

add_disk_device (*disk_type, address, name, description, disk, file_obj, ctrl_item, disk_item=None*)

Create a new disk hardware device or overwrite an existing one.

Parameters

- **disk_type** (*str*) – 'hddisk' or 'cdrom'
- **address** (*str*) – Address on controller, such as "1:0" (optional)
- **name** (*str*) – Device name string (optional)
- **description** (*str*) – Description string (optional)
- **disk** (*xml.etree.ElementTree.Element*) – Disk object to map to this device
- **file_obj** (*xml.etree.ElementTree.Element*) – File object to map to this device
- **ctrl_item** (*OVFItem*) – Controller object to serve as parent
- **disk_item** (*OVFItem*) – Existing disk device to update instead of making a new device.

Returns New or updated disk device object.

add_file (*file_path, file_id, file_obj=None, disk=None*)

Add a new file object to the VM or overwrite the provided one.

Parameters

- **file_path** (*str*) – Path to file to add
- **file_id** (*str*) – Identifier string for the file in the VM
- **file_obj** (*xml.etree.ElementTree.Element*) – Existing file object to overwrite
- **disk** (*xml.etree.ElementTree.Element*) – Existing disk object referencing file.

Returns New or updated file object

check_sanity_of_disk_device (*disk, file_obj, disk_item, ctrl_item*)

Check if the given disk is linked properly to the other objects.

Parameters

- **disk** (*xml.etree.ElementTree.Element*) – Disk object to validate
- **file_obj** (*xml.etree.ElementTree.Element*) – File object which this disk should be linked to (optional)
- **disk_item** (*OVFItem*) – Disk device object which should link to this disk (optional)
- **ctrl_item** (*OVFItem*) – Controller device object which should link to the disk_item

Raises

- **ValueMismatchError** – if the given items are not linked properly.
- **ValueUnsupportedError** – if the disk_item has a HostResource value in an unrecognized or invalid format.

config_file_to_properties (*file_path*, *user_configurable=None*)

Import each line of a text file into a configuration property.

Raises `NotImplementedError` – if the *platform* for this OVF does not define *LITERAL_CLI_STRING*

Parameters

- **file_path** (*str*) – File name to import.
- **user_configurable** (*bool*) – Should the properties be configurable at deployment time by the user?

convert_disk_if_needed (*file_path*, *kind*)

Convert the disk to a more appropriate format if needed.

- All hard disk files are converted to stream-optimized VMDK as it is the only format that VMware supports in OVA packages.
- CD-ROM iso images are accepted without change.

Parameters

- **file_path** (*str*) – Image to inspect and possibly convert
- **kind** (*str*) – Image type (harddisk/cdrom)

Returns

- *file_path*, if no conversion was required
- or a file path in *output_dir* containing the converted image

create_configuration_profile (*pid*, *label*, *description*)

Create or update a configuration profile with the given ID.

Parameters

- **pid** (*str*) – Profile identifier
- **label** (*str*) – Brief descriptive label for the profile
- **description** (*str*) – Verbose description of the profile

create_network (*label*, *description*)

Define a new network with the given label and description.

Also serves to update the description of an existing network label.

Parameters

- **label** (*str*) – Brief label for the network
- **description** (*str*) – Verbose description of the network

delete_configuration_profile (*profile*)

Delete the profile with the given ID.

static detect_type_from_name (*filename*)

Check the given filename to see if it looks like a type we support.

For our purposes, the file needs to match “*.ov[af]*” to appear to be an OVF/OVA file. We also support names like “*foo.ovf.20150101*” as those have been seen in the wild.

Does not check file contents, as the given filename may not yet exist.

Returns ‘*.ovf*’ or ‘*.ova*’

Raises `ValueUnsupportedError` – if filename doesn't match ovf/ova

`device_info_str(device_item)`

Get a one-line summary of a hardware device.

Parameters `device_item` (`OVFItem`) – Device to summarize

Returns Descriptive string such as “harddisk @ IDE 1:0”

`find_device_location(device)`

Find the controller type and address of a given device object.

Parameters `device` (`OVFItem`) – Hardware device object.

Returns (`type`, `address`), such as (“ide”, “1:0”).

`find_disk_from_file_id(file_id)`

Find the Disk that uses the given `file_id` for backing.

Parameters `file_id` (`str`) – File identifier string

Returns Disk element matching the file, or `None`

`find_empty_drive(disk_type)`

Find a disk device that exists but contains no data.

Parameters `disk_type` (`str`) – Either ‘cdrom’ or ‘harddisk’

Returns Hardware device object, or `None`.

`find_item_from_disk(disk)`

Find the disk Item that references the given Disk.

Parameters `disk` (`xml.etree.ElementTree.Element`) – Disk element

Returns `OVFItem` instance, or `None`

`find_item_from_file(file_obj)`

Find the disk Item that references the given File.

Parameters `file_obj` (`xml.etree.ElementTree.Element`) – File element

Returns `OVFItem` instance, or `None`.

`find_open_controller(controller_type)`

Find the first open slot on a controller of the given type.

Parameters `controller_type` (`str`) – ‘ide’ or ‘scsi’

Returns (`ctrl_item`, `address_string`) or (`None`, `None`)

`find_parent_from_item(item)`

Find the parent Item of the given Item.

Parameters `item` (`OVFItem`) – Item whose parent is desired

Returns `OVFItem` representing the parent device, or `None`

`generate_manifest(ovf_file)`

Construct the manifest file for this package, if possible.

Parameters `ovf_file` (`str`) – OVF descriptor file path

Returns True if the manifest was successfully generated, False if not successful (such as if checksum helper tools are unavailable).

`get_capacity_from_disk(disk)`

Get the capacity of the given Disk in bytes.

Parameters **disk** (*xml.etree.ElementTree.Element*) – Disk element to inspect

Return type int

get_common_subtype (*device_type*)

Get the sub-type common to all devices of the given type.

Parameters **device_type** (*str*) – Device type such as 'ide' or 'memory'.

Returns None, if multiple such devices exist and they do not all have the same sub-type.

Returns Subtype string common to all devices of the type.

get_file_ref_from_disk (*disk*)

Get the file reference from the given opaque disk object.

Parameters **disk** (*xml.etree.ElementTree.Element*) – 'Disk' element

Returns 'fileRef' attribute value of this element

get_id_from_disk (*disk*)

Get the identifier string associated with the given Disk object.

Parameters **disk** (*xml.etree.ElementTree.Element*) – Disk object to inspect

Return type string

get_id_from_file (*file_obj*)

Get the file ID from the given opaque file object.

Parameters **file_obj** (*xml.etree.ElementTree.Element*) – 'File' element

Returns 'id' attribute value of this element

get_nic_count (*profile_list*)

Get the number of NICs under the given profile(s).

Parameters **profile_list** (*list*) – Profile(s) of interest.

Return type dict

Returns { profile_name : nic_count }

get_path_from_file (*file_obj*)

Get the file path from the given opaque file object.

Parameters **file_obj** (*xml.etree.ElementTree.Element*) – 'File' element

Returns 'href' attribute value of this element

get_property_value (*key*)

Get the value of the given property.

Parameters **key** (*str*) – Property identifier

Returns Value of this property, or None

get_serial_connectivity (*profile*)

Get the serial port connectivity strings under the given profile.

Parameters **profile** (*str*) – Profile of interest.

Returns List of connectivity strings

get_serial_count (*profile_list*)

Get the number of serial ports under the given profile(s).

Return type dict

Returns { profile_name : serial_count }

get_subtype_from_device (*device*)

Get the sub-type of the given opaque device object.

Parameters *device* (*OVFItem*) – Device object to query

Returns None, or string such as ‘virtio’ or ‘lsilogic’, or list of strings

get_type_from_device (*device*)

Get the type of the given device.

Parameters *device* (*OVFItem*) – Device object to query

Returns string such as ‘ide’ or ‘memory’

info_string (*width=79, verbosity_option=None*)

Get a descriptive string summarizing the contents of this OVF.

Parameters

- **width** (*int*) – Line length to wrap to where possible.
- **verbosity_option** (*str*) – ‘brief’, None (default), or ‘verbose’

Returns Wrapped, appropriately verbose string.

profile_info_list (*width=79, verbose=False*)

Get a list describing available configuration profiles.

Parameters

- **width** (*int*) – Line length to wrap to if possible
- **verbose** (*str*) – if True, generate multiple lines per profile

Returns (header, list)

profile_info_string (*width=79, verbosity_option=None*)

Get a string summarizing available configuration profiles.

Parameters

- **width** (*int*) – Line length to wrap to if possible
- **verbosity_option** (*str*) – ‘brief’, None (default), or ‘verbose’

Returns Appropriately formatted and verbose string.

remove_file (*file_obj, disk=None, disk_drive=None*)

Remove the given file object from the VM.

Parameters

- **file_obj** (*xml.etree.ElementTree.Element*) – File object to remove
- **disk** (*xml.etree.ElementTree.Element*) – Disk object referencing file
- **disk_drive** (*OVFItem*) – Disk drive mapping file to a device

search_from_controller (*controller, address*)

From the controller type and device address, look for existing disk.

This implementation uses the parameters to find matching controller and disk *Item* elements, then using the disk *Item* to find matching *File* and/or *Disk*.

Parameters

- **controller** (*str*) – ‘ide’ or ‘scsi’

- **address** (*str*) – Device address such as '1:0'

Returns (*file*, *disk*, *ctrl_item*, *disk_item*), any or all of which may be *None*

search_from_file_id (*file_id*)

From the given file ID, try to find any existing objects.

This implementation uses the given *file_id* to find a matching *File* in the OVF, then using that to find a matching *Disk* and *Item* entries.

Parameters **file_id** (*str*) – Filename to search from

Returns (*file*, *disk*, *ctrl_item*, *disk_item*), any or all of which may be *None*

search_from_filename (*filename*)

From the given filename, try to find any existing objects.

This implementation uses the given *filename* to find a matching *File* in the OVF, then using that to find a matching *Disk* and *Item* entries.

Parameters **filename** (*str*) – Filename to search from

Returns (*file*, *disk*, *ctrl_item*, *disk_item*), any or all of which may be *None*

set_capacity_of_disk (*disk*, *capacity_bytes*)

Set the storage capacity of the given *Disk*.

Tries to use the most human-readable form possible (i.e., 8 GiB instead of 8589934592 bytes).

Parameters

- **disk** (*xml.etree.ElementTree.Element*) – *Disk* to update
- **capacity_bytes** (*int*) – *Disk* capacity, in bytes

set_cpu_count (*cpus*, *profile_list*)

Set the number of CPUs.

Parameters

- **cpus** (*int*) – Number of CPUs
- **profile_list** (*list*) – Change only the given profiles

set_ide_subtypes (*type_list*, *profile_list*)

Set the device subtype(s) for the IDE controller(s).

Parameters

- **type_list** (*list*) – IDE subtype string list
- **profile_list** (*list*) – Change only the given profiles

set_memory (*megabytes*, *profile_list*)

Set the amount of RAM, in megabytes.

Parameters

- **megabytes** (*int*) – Memory value, in megabytes
- **profile_list** (*list*) – Change only the given profiles

set_nic_count (*count*, *profile_list*)

Set the given profile(s) to have the given number of NICs.

Parameters

- **count** (*int*) – number of NICs

- **profile_list** (*list*) – Change only the given profiles

set_nic_mac_addresses (*mac_list*, *profile_list*)

Set the MAC addresses for NICs under the given profile(s).

Note: If the length of *mac_list* is less than the number of NICs, will use the last entry in the list for all remaining NICs.

Parameters

- **mac_list** (*list*) – List of MAC addresses to assign to NICs
- **profile_list** (*list*) – Change only the given profiles

set_nic_names (*name_list*, *profile_list*)

Set the device names for NICs under the given profile(s).

Parameters

- **name_list** (*list*) – List of names to assign.
- **profile_list** (*list*) – Change only the given profiles

set_nic_networks (*network_list*, *profile_list*)

Set the NIC to network mapping for NICs under the given profile(s).

Note: If the length of *network_list* is less than the number of NICs, will use the last entry in the list for all remaining NICs.

Parameters

- **network_list** (*list*) – List of networks to map NICs to
- **profile_list** (*list*) – Change only the given profiles

set_nic_types (*type_list*, *profile_list*)

Set the hardware type(s) for NICs.

Parameters

- **type_list** (*list*) – NIC hardware type(s)
- **profile_list** (*list*) – Change only the given profiles.

set_property_value (*key*, *value*, *user_configurable=None*, *property_type=None*, *label=None*, *description=None*)

Set the value of the given property (converting value if needed).

Parameters

- **key** (*str*) – Property identifier
- **value** – Value to set for this property
- **user_configurable** (*bool*) – Should this property be configurable at deployment time by the user?
- **property_type** (*str*) – Value type - ‘string’ or ‘boolean’
- **label** (*str*) – Brief explanatory label for this property

- **description** (*str*) – Detailed description of this property

Returns the (converted) value that was set.

set_scsi_subtypes (*type_list*, *profile_list*)

Set the device subtype(s) for the SCSI controller(s).

Parameters

- **type_list** (*list*) – SCSI subtype string list
- **profile_list** (*list*) – Change only the given profiles

set_serial_connectivity (*conn_list*, *profile_list*)

Set the serial port connectivity under the given profile(s).

Parameters

- **conn_list** (*list*) – List of connectivity strings
- **profile_list** (*list*) – Change only the given profiles

set_serial_count (*count*, *profile_list*)

Set the given profile(s) to have the given number of serial ports.

Parameters

- **count** (*int*) – Number of serial ports
- **profile_list** (*list*) – Change only the given profiles

tar (*ovf_descriptor*, *tar_file*)

Create a .ova tar file based on the given OVF descriptor.

Parameters

- **ovf_descriptor** (*str*) – File path for an OVF descriptor
- **tar_file** (*str*) – File path for the desired OVA archive.

untar (*file_path*)

Untar the OVF descriptor from an .ova to the working directory.

Parameters **file_path** (*str*) – OVA file path

Raises **VMInitError** – if the given file does not represent a valid OVA archive.

Returns Path to extracted OVF descriptor

validate_and_update_file_references ()

Check all File entries to make sure they are valid and up to date.

Helper method for `write()`.

validate_and_update_networks ()

Make sure all defined networks are actually used by NICs.

Delete any networks that are unused and warn the user. Helper method for `write()`.

validate_hardware ()

Check sanity of hardware properties for this VM/product/platform.

Returns True if hardware is sane, False if not.

write ()

Write OVF or OVA to `output_file`, if set.

INFO_STRING_DISK_COLUMNS_WIDTH = 41

INFO_STRING_DISK_TEMPLATE = '{{0:{0}}} {{1:>9}} {{2:>9}} {{3:..20}}'

INFO_STRING_FILE_TEMPLATE = '{{0:{0}}} {{1:>9}}'

PROFILE_INFO_TEMPLATE = '{{0:{0}}} {{1:>4}} {{2:>9}} {{3:>4}} {{4:>7}} {{5:>14}}'

application_url

Application URL string (XML AppUrl element).

config_profiles

The list of supported configuration profiles.

If this OVF has no defined profiles, returns an empty list. If there is a default profile, it will be first in the list.

environment_properties

The array of environment properties.

Returns Array of dicts (one per property) with the keys "key", "value", "qualifiers", "type", "user_configurable", "label", and "description".

environment_transports

The list of environment transport methods.

Return type list[str]

network_descriptions

The list of network descriptions currently defined in this VM.

Return type list[str]

networks

The list of network names currently defined in this VM.

Return type list[str]

output_file

OVF or OVA file that will be created or updated by `write()`.

Raises **ValueUnsupportedError** – if `detect_type_from_name()` fails

ovf_version

Float representing the OVF specification version in use.

Supported values at present are 0.9, 1.0, and 2.0.

platform

The platform type, as determined from the OVF descriptor.

Type Class object - *GenericPlatform* or a more-specific subclass if recognized as such.

product

Short descriptive product string (XML Product element).

product_class

The product class identifier, such as com.cisco.csr1000v.

product_url

Product URL string (XML ProductUrl element).

system_types

List of virtual system type(s) supported by this virtual machine.

For an OVF, this corresponds to the VirtualSystemType element.

vendor

Short descriptive vendor string (XML `Vendor` element).

vendor_url

Vendor URL string (XML `VendorUrl` element).

version_long

Long descriptive version string (XML `FullVersion` element).

version_short

Short descriptive version string (XML `Version` element).

byte_count (*base_val*, *multiplier*)

Convert an OVF-style value + multiplier into decimal byte count.

Inverse operation of *factor_bytes()*.

```
>>> byte_count("128", "byte * 2^20")
134217728
>>> byte_count("512", "MegaBytes")
536870912
```

Parameters

- **base_val** (*str*) – Base value string (value of `ovf:capacity`, etc.)
- **multiplier** (*str*) – Multiplier string (value of `ovf:capacityAllocationUnits`, etc.)

Returns Number of bytes

Return type `int`

byte_string (*byte_value*, *base_shift=0*)

Pretty-print the given bytes value.

```
>>> byte_string(512)
'512 B'
>>> byte_string(512, 2)
'512 MiB'
>>> byte_string(65536, 2)
'64 GiB'
>>> byte_string(65547)
'64.01 KiB'
>>> byte_string(65530, 3)
'63.99 TiB'
>>> byte_string(1023850)
'999.9 KiB'
>>> byte_string(1024000)
'1000 KiB'
>>> byte_string(1048575)
'1024 KiB'
>>> byte_string(1049200)
'1.001 MiB'
>>> byte_string(2560)
'2.5 KiB'
```

Parameters

- **byte_value** (*float*) – Value
- **base_shift** (*int*) – Base value of `byte_value` (0 = bytes, 1 = KiB, 2 = MiB, etc.)

Returns Pretty-printed byte string such as “1.00 GiB”

factor_bytes (*byte_value*)

Convert a byte count into OVF-style bytes + multiplier.

Inverse operation of *byte_count* ()

```
>>> factor_bytes(134217728)
('128', 'byte * 2^20')
>>> factor_bytes(134217729)
('134217729', 'byte')
```

Parameters *byte_value* (*int*) – Number of bytes

Returns (*base_val*, *multiplier*)

COT.ovf.hardware module

Representation of OVF hardware definitions.

Classes and Exceptions

<i>OVFHardware</i>	Helper class for OVF.
<i>OVFHardwareDataError</i>	The input data used to construct an <i>OVFHardware</i> is not sane.

exception **OVFHardwareDataError**

Bases: `exceptions.Exception`

The input data used to construct an *OVFHardware* is not sane.

class **OVFHardware** (*ovf*)

Bases: `object`

Helper class for OVF.

Represents all hardware items defined by this OVF; i.e., the contents of all Items in the VirtualHardwareSection.

Fundamentally it’s just a dict of *OVFItem* objects with a bunch of helper methods.

clone_item (*parent_item*, *profile_list*)

Clone an *OVFItem* to create a new instance.

Parameters

- **parent_item** (*OVFItem*) – Instance to clone from
- **profile_list** (*list*) – List of profiles to clone into

Returns (*instance*, *ovfitem*)

delete_item (*item*)

Delete the given *OVFItem*.

find_all_items (*resource_type=None*, *properties=None*, *profile_list=None*)

Find all items matching the given type, properties, and profiles.

Parameters

- **resource_type** (*str*) – Resource type string like ‘scsi’ or ‘serial’
- **properties** (*dict* [*property*, *value*]) – Property values to match

- **profile_list** (*list*) – List of profiles to filter on

Returns list of OVFIItem instances

find_item (*resource_type=None, properties=None, profile=None*)

Find the only OVFIItem of the given *resource_type*.

Parameters

- **resource_type** (*str*) – Resource type string like ‘scsi’ or ‘serial’
- **properties** (*dict[property, value]*) – Property values to match
- **profile** (*str*) – Single profile ID to search within

Return type OVFIItem or None

Raises **LookupError** – if more than one such Item exists.

find_unused_instance_id ()

Find the first available InstanceID number.

Return type string

get_item_count (*resource_type, profile*)

Wrapper for *get_item_count_per_profile* ().

Parameters

- **resource_type** (*str*) –
- **profile** (*str*) – Single profile identifier string to look up.

Returns Number of items of this type in this profile.

get_item_count_per_profile (*resource_type, profile_list*)

Get the number of Items of the given type per profile.

Items present under “no profile” will be counted against the total for each profile.

Parameters

- **resource_type** (*str*) –
- **profile_list** (*list*) – List of profiles to filter on (default: apply across all profiles)

Return type dict[profile, count]

item_match (*item, resource_type, properties, profile_list*)

Check whether the given item matches the given filters.

new_item (*resource_type, profile_list=None*)

Create a new OVFIItem of the given type.

Parameters

- **resource_type** (*str*) –
- **profile_list** (*list*) – Profiles the new item should belong to

Returns (instance, ovfitem)

set_item_count_per_profile (*resource_type, count, profile_list*)

Set the number of items of a given type under the given profile(s).

If the new count is greater than the current count under this profile, then additional instances that already exist under another profile will be added to this profile, starting with the lowest-sequence instance not already present, and only as a last resort will new instances be created.

If the new count is less than the current count under this profile, then the highest-numbered instances will be removed preferentially.

Parameters

- **resource_type** (*str*) – ‘cpu’, ‘harddisk’, etc.
- **count** (*int*) – Desired number of items
- **profile_list** (*list*) – List of profiles to filter on (default: apply across all profiles)

set_item_values_per_profile (*resource_type*, *prop_name*, *value_list*, *profile_list*, *default=None*)

Set value(s) for a property of multiple items of a type.

Parameters

- **resource_type** (*str*) – Device type such as ‘harddisk’ or ‘cpu’
- **prop_name** (*str*) – Property name to update
- **value_list** (*list*) – List of values to set (one value per item of the given resource_type)
- **profile_list** (*list*) – List of profiles to filter on (default: apply across all profiles)
- **default** (*str*) – If there are more matching items than entries in value_list, set extra items to this value

set_value_for_all_items (*resource_type*, *prop_name*, *new_value*, *profile_list*, *create_new=False*)

Set a property to the given value for all items of the given type.

If no items of the given type exist, will create a new Item if create_new is set to True; otherwise will log a warning and do nothing.

Parameters

- **resource_type** (*str*) – Resource type such as ‘cpu’ or ‘harddisk’
- **prop_name** (*str*) – Property name to update
- **new_value** (*str*) – New value to set the property to
- **profile_list** (*list*) – List of profiles to filter on (default: apply across all profiles)
- **create_new** (*boolean*) – Whether to create a new entry if no items of this resource_type presently exist.

update_existing_item_count_per_profile (*resource_type*, *count*, *profile_list*)

Change profile membership of existing items as needed.

Helper method for `set_item_count_per_profile()`.

Returns (count_dict, items_to_add, last_item)

update_xml ()

Regenerate all Items under the VirtualHardwareSection, if needed.

Will do nothing if no Items have been changed.

COT.ovf.item module

Module for working with individual hardware elements in an OVF.

Represents all variations of a given hardware Item amongst different hardware configuration profiles.

Functions

<code>list_union</code>	Get union of lists.
-------------------------	---------------------

Classes and Exceptions

<code>OVFItem</code>	Helper class for OVF.
<code>OVFItemDataError</code>	Data to be added to an <code>OVFItem</code> conflicts with existing data.

exception `OVFItemDataError`

Bases: `exceptions.Exception`

Data to be added to an `OVFItem` conflicts with existing data.

class `OVFItem` (`ovf, item=None`)

Bases: `object`

Helper class for OVF.

Represents all variations of a given hardware `Item` amongst different hardware configuration profiles.

In essence, it is:

- a dict of `Item` properties (indexed by element name)
- each of which is a dict of sets of profiles (indexed by element value)

`add_item` (`item`)

Add the given `Item` element to this `OVFItem`.

Parameters `item` (`xml.etree.ElementTree.Element`) – XML `Item` element

Raises `OVFItemDataError` – if the new `Item` conflicts with existing data already in the `OVFItem`.

`add_profile` (`new_profile, from_item=None`)

Add a new profile to this item.

Parameters

- **`new_profile`** (`str`) – Profile name to add
- **`from_item`** (`OVFItem`) – Item to inherit properties from. If unset, this defaults to `self`.

`all_profiles` (`name, default=None`)

Superset of all profiles for which this name has a value.

`generate_items` ()

Get a list of `Item` XML elements derived from this object's data.

Return type `list[xml.etree.ElementTree.Element]`

`get` (`tag`)

Get the dict associated with the given XML tag, if any.

Parameters `tag` (`str`) – XML tag to look up

Return type `dict`

Returns Dictionary of values associated with this tag (TODO?)

`get_all_values` (`tag`)

Get the list of all value strings for the given tag.

Parameters **tag** (*str*) – Tag to retrieve value for

Return type list

get_nonintersecting_set_list ()

Identify the minimal non-intersecting set of profiles.

Returns List of profile-set strings.

get_value (*tag*, *profiles=None*)

Get the value for the given tag under the given profiles.

If the tag does not exist under these profiles, or the tag values differ across the profiles, returns `None`.

Parameters

- **tag** (*str*) – Tag to retrieve value for
- **profiles** (*set of strings*) – set of profile names, or `None`

Returns Value string or list, or `None`

has_profile (*profile*)

Check if this Item exists under the given profile.

Parameters **profile** (*str*) – Profile name

Return type boolean

property_profiles (*name*, *value*)

Get set of profiles associated with a property name and value.

property_values (*name*)

Get list of values known for a given property name.

remove_profile (*profile*, *split_default=True*)

Remove all trace of the given profile from this item.

Parameters

- **profile** (*str*) – Profile name to remove
- **split_default** (*bool*) – If `False`, do not split out ‘default’ profile items to specifically exclude this profile. Used when the profile being removed will no longer exist anywhere and so ‘default’ will continue to exclude this profile.

set_property (*name*, *value*, *profiles=None*, *overwrite=True*)

Store the value and profiles associated with it for the given name.

Parameters

- **name** (*str*) – Property name
- **value** (*str*) – Value associated with *name*
- **profiles** (*list[str]*) – If `None`, set for all profiles currently known to this item, else set only for the given list of profiles.
- **overwrite** (*boolean*) – Whether to permit overwriting of existing value set in this item.

Raises **OVFItemDataError** – if a value is already defined and would be overwritten, unless `overwrite` is `True`

validate ()

Verify that the OVFItem describes a valid set of items.

Also clean up any oddities (like a property value assigned to ‘all profiles’ and also redundantly to a specific profile).

Raises `RuntimeError` – if validation fails and self-repair is impossible.

`value_add_wildcards` (*name, value, profiles*)

Add wildcard placeholders to a string that may need updating.

`value_replace_wildcards` (*name, value, profiles*)

Replace wildcards with actual values.

`ATTRIB_KEY_SUFFIX` = ‘{Item attribute}’

`ELEMENT_KEY_SUFFIX` = ‘{custom element}’

`properties` = `None`

Dict of dicts. `properties[name][value]` = (profile1, profile2).

`property_names`

List of names of all properties known to this `OVFItem`.

`list_union` (**lists*)

Get union of lists.

`COT.ovf.name_helper` module

Module for handling the differences in XML between OVF spec versions.

Functions

<code>name_helper</code>	Generate an instance of the correct <code>OVFNameHelper</code> variant class.
--------------------------	---

Classes and Exceptions

<code>OVFNameHelper1</code>	Helper class for OVF version 1.x.
<code>OVFNameHelper0</code>	Helper class for OVF of versions prior to 1.0.
<code>OVFNameHelper2</code>	Helper class for OVF of version 2.x.

class `OVFNameHelper0`

Bases: `COT.ovf.name_helper.OVFNameHelper1`

Helper class for OVF of versions prior to 1.0.

Provides string constants for easier lookup of various OVF XML elements and attributes.

`NSM` = {‘vssd’: ‘http://schemas.dmtf.org/wbem/wscim/1/cim-schema/2/CIM_VirtualSystemSettingData’, ‘rasd’: ‘http://schemas.dmtf.org/wbem/wscim/1/cim-schema/2/CIM_VirtualSystemSettingData’}

class `OVFNameHelper1`

Bases: `object`

Helper class for OVF version 1.x.

Provides string constants for easier lookup of various OVF XML elements and attributes.

Version-specific subclasses below provide variant properties.

`item_tag_for_namespace` (*ns*)

Get the item tag for the given XML namespace.

`namespace_for_item_tag` (*tag*)

Get the XML namespace for the given item tag.

namespace_for_resource_type (*resource_type*)

Get the XML namespace for the given ResourceType.

NSM = {'vssd': 'http://schemas.dmtf.org/wbem/wscim/1/cim-schema/2/CIM_VirtualSystemSettingData', 'rasd': 'http://schemas.dmtf.org/wbem/wscim/1/cim-schema/2/CIM_VirtualSystemSettingData', 'ovf': 'http://schemas.dmtf.org/ovf/envelope/1'}

RES_MAP = {'ib': '9', 'usb': '23', 'floppy': '14', 'dvd': '16', 'iscsi': '8', 'harddisk': '17', 'parallel': '22', 'sata': '20', 'fc': '21'}

class OVFNameHelper2

Bases: *COT.ovf.name_helper.OVFNameHelper1*

Helper class for OVF of version 2.x. TODO.

Provides string constants for easier lookup of various OVF XML elements and attributes.

NSM = {'vssd': 'http://schemas.dmtf.org/wbem/wscim/1/cim-schema/2/CIM_VirtualSystemSettingData', 'rasd': 'http://schemas.dmtf.org/wbem/wscim/1/cim-schema/2/CIM_VirtualSystemSettingData', 'ovf': 'http://schemas.dmtf.org/ovf/envelope/1'}

name_helper (*version*)

Generate an instance of the correct OVFNameHelper variant class.

Parameters **version** (*float*) – OVF specification version to use, such as 0.9, 1.0, or 2.0

Returns Instance of OVFNameHelper[012] as appropriate.

Indices and tables

- `genindex`
- `modindex`
- `search`

- .
- COT.add_disk, 50
- COT.add_file, 53
- COT.cli, 74
- COT.data_validation, 64
- COT.deploy, 53
- COT.deploy_esxi, 55
- COT.edit_hardware, 57
- COT.edit_product, 59
- COT.edit_properties, 60
- COT.file_reference, 68
- COT.help, 61
- COT.helpers, 78
- COT.helpers.api, 79
- COT.helpers.fatdisk, 83
- COT.helpers.helper, 81
- COT.helpers.mkisofs, 84
- COT.helpers.ovftool, 84
- COT.helpers.qemu_img, 85
- COT.helpers.vmdktool, 86
- COT.info, 61
- COT.inject_config, 62
- COT.install_helpers, 63
- COT.ovf, 87
- COT.ovf.hardware, 99
- COT.ovf.item, 101
- COT.ovf.name_helper, 104
- COT.ovf.ovf, 87
- COT.platforms, 69
- COT.remove_file, 63
- COT.submodule, 49
- COT.ui_shared, 73
- COT.vm_context_manager, 46
- COT.vm_description, 37
- COT.vm_factory, 46
- COT.xml_file, 46

C

COT, 37

Symbols

`__init__()` (Helper method), 82

A

`add_child()` (COT.xml_file.XML class method), 47
`add_controller_device()` (OVF method), 88
`add_controller_device()` (VMDescription method), 38
`add_disk()` (OVF method), 88
`add_disk()` (VMDescription method), 38
`add_disk_device()` (OVF method), 89
`add_disk_device()` (VMDescription method), 38
`add_disk_worker()` (in module COT.add_disk), 51
`add_file()` (OVF method), 89
`add_file()` (VMDescription method), 38
`add_item()` (OVFItem method), 102
`add_profile()` (OVFItem method), 102
`add_subparser()` (CLI method), 75
`add_to_archive()` (FileInTAR method), 68
`add_to_archive()` (FileOnDisk method), 68
`address` (COTAddDisk attribute), 51
`all_profiles()` (OVFItem method), 102
`alphanum_split()` (in module COT.data_validation), 65
`application_url` (COTEditProduct attribute), 60
`application_url` (OVF attribute), 97
`apt_install()` (COT.helpers.helper.Helper class method), 82
`args_to_dict()` (CLI static method), 75
`ATTRIB_KEY_SUFFIX` (OVFItem attribute), 104

B

`BOOTSTRAP_DISK_TYPE` (GenericPlatform attribute), 70
`BOOTSTRAP_DISK_TYPE` (IOSv attribute), 71
`byte_count()` (in module COT.ovf.ovf), 98
`byte_string()` (in module COT.ovf.ovf), 98

C

`call_helper()` (Helper method), 82
`canonicalize_helper()` (in module COT.data_validation), 65

`canonicalize_ide_subtype()` (in module COT.data_validation), 66
`canonicalize_nic_subtype()` (in module COT.data_validation), 66
`canonicalize_scsi_subtype()` (in module COT.data_validation), 66
`check_for_conflict()` (in module COT.data_validation), 66
`check_sanity_of_disk_device()` (OVF method), 89
`check_sanity_of_disk_device()` (VMDescription method), 39
`choose_from_list()` (UI method), 73
`CLI` (class in COT.cli), 75
`clone_item()` (OVFHardware method), 99
`close()` (FileInTAR method), 68
`close()` (FileOnDisk method), 69
`config_file` (COTEditProperties attribute), 61
`config_file` (COTInjectConfig attribute), 62
`config_file_to_properties()` (OVF method), 89
`config_file_to_properties()` (VMDescription method), 39
`config_profiles` (OVF attribute), 97
`config_profiles` (VMDescription attribute), 45
`CONFIG_TEXT_FILE` (CSR1000V attribute), 70
`CONFIG_TEXT_FILE` (GenericPlatform attribute), 70
`CONFIG_TEXT_FILE` (IOSv attribute), 71
`CONFIG_TEXT_FILE` (IOSXRv attribute), 71
`CONFIG_TEXT_FILE` (IOSXRvLC attribute), 72
`CONFIG_TEXT_FILE` (NXOSv attribute), 73
`configuration` (COTDeploy attribute), 54
`confirm()` (CLI method), 75
`confirm()` (UI method), 73
`confirm_elements()` (in module COT.add_disk), 52
`confirm_or_die()` (UI method), 73
`controller` (COTAddDisk attribute), 51
`controller_type_for_device()` (COT.platforms.CSR1000V class method), 70
`controller_type_for_device()` (COT.platforms.GenericPlatform class method), 69
`convert_disk_if_needed()` (OVF method), 90
`convert_disk_if_needed()` (VMDescription method), 39
`convert_disk_image()` (in module COT.helpers.api), 79

convert_disk_image() (QEMUImg method), 85
convert_disk_image() (VmdkTool method), 86
copy_to() (FileInTAR method), 68
copy_to() (FileOnDisk method), 69
COT (module), 37
COT.add_disk (module), 50
COT.add_file (module), 53
COT.cli (module), 74
COT.data_validation (module), 64
COT.deploy (module), 53
COT.deploy_esxi (module), 55
COT.edit_hardware (module), 57
COT.edit_product (module), 59
COT.edit_properties (module), 60
COT.file_reference (module), 68
COT.help (module), 61
COT.helpers (module), 78
COT.helpers.api (module), 79
COT.helpers.fatdisk (module), 83
COT.helpers.helper (module), 81
COT.helpers.mkisofs (module), 84
COT.helpers.ovftool (module), 84
COT.helpers.qemu_img (module), 85
COT.helpers.vmdktool (module), 86
COT.info (module), 61
COT.inject_config (module), 62
COT.install_helpers (module), 63
COT.ovf (module), 87
COT.ovf.hardware (module), 99
COT.ovf.item (module), 101
COT.ovf.name_helper (module), 104
COT.ovf.ovf (module), 87
COT.platforms (module), 69
COT.remove_file (module), 63
COT.submodule (module), 49
COT.ui_shared (module), 73
COT.vm_context_manager (module), 46
COT.vm_description (module), 37
COT.vm_factory (module), 46
COT.xml_file (module), 46
COTAddDisk (class in COT.add_disk), 51
COTAddFile (class in COT.add_file), 53
COTDeploy (class in COT.deploy), 53
COTDeployESXi (class in COT.deploy_esxi), 55
COTEditHardware (class in COT.edit_hardware), 57
COTEditProduct (class in COT.edit_product), 59
COTEditProperties (class in COT.edit_properties), 60
COTGenericSubmodule (class in COT.submodule), 49
COTHelp (class in COT.help), 61
COTInfo (class in COT.info), 61
COTInjectConfig (class in COT.inject_config), 62
COTInstallHelpers (class in COT.install_helpers), 63
COTReadOnlySubmodule (class in COT.submodule), 49
COTRemoveFile (class in COT.remove_file), 63

COTSubmodule (class in COT.submodule), 50
cpus (COTEditHardware attribute), 57
create() (COT.vm_factory.VMFactory class method), 46
create_blank_disk() (QEMUImg method), 86
create_configuration_profile() (OVF method), 90
create_configuration_profile() (VMDescription method), 39
create_disk_image() (in module COT.helpers.api), 80
create_install_dir() (in module COT.helpers.api), 80
create_iso() (MkIsoFS method), 84
create_network() (OVF method), 90
create_network() (VMDescription method), 39
create_parser() (CLI method), 75
create_raw_image() (FatDisk method), 83
create_subparser() (COTAddDisk method), 51
create_subparser() (COTAddFile method), 53
create_subparser() (COTDeploy method), 54
create_subparser() (COTDeployESXi method), 56
create_subparser() (COTEditHardware method), 57
create_subparser() (COTEditProduct method), 59
create_subparser() (COTEditProperties method), 60
create_subparser() (COTGenericSubmodule method), 49
create_subparser() (COTHelp method), 61
create_subparser() (COTInfo method), 61
create_subparser() (COTInjectConfig method), 62
create_subparser() (COTInstallHelpers method), 63
create_subparser() (COTRemoveFile method), 63
create_subparsers() (CLI method), 75
CSR1000V (class in COT.platforms), 70

D

datastore (COTDeployESXi attribute), 56
default_config_profile (VMDescription attribute), 45
default_confirm_response (UI attribute), 74
delete_all_other_profiles (COTEditHardware attribute), 57
delete_configuration_profile() (OVF method), 90
delete_configuration_profile() (VMDescription method), 39
delete_item() (OVFHardware method), 99
description (COTAddDisk attribute), 51
descriptions (COTEditProperties attribute), 61
destroy() (COTGenericSubmodule method), 49
destroy() (VMDescription method), 40
detect_type_from_name()
 (COT.vm_description.VMDescription class method), 40
detect_type_from_name() (OVF static method), 90
device_address() (in module COT.data_validation), 66
device_info_str() (OVF method), 91
disk_image (COTAddDisk attribute), 51
disk_type (COTAddDisk attribute), 51
diskname (COTAddDisk attribute), 51
download_and_expand() (in module COT.helpers.api), 80

E

edit_properties_interactive() (COTEditProperties method), 60
 ELEMENT_KEY_SUFFIX (OVFItem attribute), 104
 environment_properties (OVF attribute), 97
 environment_properties (VMDescription attribute), 45
 environment_transports (OVF attribute), 97
 environment_transports (VMDescription attribute), 45
 exists() (FileInTAR method), 68
 exists() (FileOnDisk method), 69
 expand_list_wildcard() (in module COT.edit_hardware), 58

F

factor_bytes() (in module COT.ovf.ovf), 99
 FatDisk (class in COT.helpers.fatdisk), 83
 file (COTAddFile attribute), 53
 file_id (COTAddDisk attribute), 51
 file_id (COTAddFile attribute), 53
 file_id (COTRemoveFile attribute), 64
 file_path (COTRemoveFile attribute), 64
 FileInTAR (class in COT.file_reference), 68
 FileOnDisk (class in COT.file_reference), 68
 fill_examples() (CLI method), 76
 fill_examples() (UI method), 73
 fill_usage() (CLI method), 76
 fill_usage() (UI method), 74
 find_all_children() (COT.xml_file.XML class method), 47
 find_all_items() (OVFHardware method), 99
 find_child() (COT.xml_file.XML class method), 47
 find_device_location() (OVF method), 91
 find_device_location() (VMDescription method), 40
 find_disk_from_file_id() (OVF method), 91
 find_empty_drive() (OVF method), 91
 find_empty_drive() (VMDescription method), 40
 find_executable() (Helper static method), 82
 find_item() (OVFHardware method), 100
 find_item_from_disk() (OVF method), 91
 find_item_from_file() (OVF method), 91
 find_open_controller() (OVF method), 91
 find_open_controller() (VMDescription method), 40
 find_parent_from_item() (OVF method), 91
 find_unused_instance_id() (OVFHardware method), 100
 finished() (COTGenericSubmodule method), 49
 finished() (COTSubmodule method), 50
 fixup_ovftool_args() (COTDeployESXi method), 56
 fixup_serial_ports() (COTDeployESXi method), 56
 force (UI attribute), 74
 formatter() (in module COT.cli), 78
 from_cli_string() (COT.deploy.SerialConnection class method), 55
 full_version (COTEditProduct attribute), 60

G

generate_items() (OVFItem method), 102
 generate_manifest() (OVF method), 91
 generic_parser (COTDeploy attribute), 54
 GenericPlatform (class in COT.platforms), 69
 get() (OVFItem method), 102
 get_all_values() (OVFItem method), 102
 get_capacity_from_disk() (OVF method), 91
 get_checksum() (in module COT.helpers.api), 80
 get_common_subtype() (OVF method), 92
 get_common_subtype() (VMDescription method), 40
 get_disk_capacity() (in module COT.helpers.api), 80
 get_disk_capacity() (QEMUImg method), 86
 get_disk_format() (in module COT.helpers.api), 81
 get_disk_format() (QEMUImg method), 86
 get_file_ref_from_disk() (OVF method), 92
 get_file_ref_from_disk() (VMDescription method), 40
 get_id_from_disk() (OVF method), 92
 get_id_from_disk() (VMDescription method), 40
 get_id_from_file() (OVF method), 92
 get_id_from_file() (VMDescription method), 40
 get_input() (CLI method), 76
 get_input() (UI method), 74
 get_item_count() (OVFHardware method), 100
 get_item_count_per_profile() (OVFHardware method), 100
 get_nic_count() (OVF method), 92
 get_nic_count() (VMDescription method), 40
 get_nonintersecting_set_list() (OVFItem method), 103
 get_ns() (COT.xml_file.XML class method), 47
 get_object_from_connection() (in module COT.deploy_esxi), 57
 get_password() (CLI method), 77
 get_password() (UI method), 74
 get_path_from_file() (OVF method), 92
 get_path_from_file() (VMDescription method), 41
 get_property_value() (OVF method), 92
 get_property_value() (VMDescription method), 41
 get_serial_connectivity() (OVF method), 92
 get_serial_connectivity() (VMDescription method), 41
 get_serial_count() (OVF method), 92
 get_serial_count() (VMDescription method), 41
 get_subtype_from_device() (OVF method), 93
 get_subtype_from_device() (VMDescription method), 41
 get_type_from_device() (OVF method), 93
 get_type_from_device() (VMDescription method), 41
 get_value() (OVFItem method), 103
 guess_controller_type() (in module COT.add_disk), 52
 guess_disk_type_from_extension() (in module COT.add_disk), 52
 guess_file_format_from_path() (in module COT.helpers.helper), 83
 guess_list_wildcard() (in module COT.edit_hardware), 59
 guess_manpath() (in module COT.install_helpers), 63

`guess_nic_name()` (COT.platforms.CSR1000V class method), 70
`guess_nic_name()` (COT.platforms.GenericPlatform class method), 69
`guess_nic_name()` (COT.platforms.IOSv class method), 71
`guess_nic_name()` (COT.platforms.IOSXRv class method), 71
`guess_nic_name()` (COT.platforms.IOSXRvLC class method), 72
`guess_nic_name()` (COT.platforms.IOSXRvRP class method), 72
`guess_nic_name()` (COT.platforms.NXOSv class method), 72

H

`has_profile()` (OVFItem method), 103
`Helper` (class in COT.helpers.helper), 81
`HelperError`, 81
`HelperNotFoundError`, 81
`host` (COTDeployESXi attribute), 56
`hypervisor` (COTDeploy attribute), 54

I

`ide_subtype` (COTEditHardware attribute), 57
`ide_subtypes` (COTEditHardware attribute), 58
`info_string()` (OVF method), 93
`info_string()` (VMDescription method), 41
`INFO_STRING_DISK_COLUMNS_WIDTH` (OVF attribute), 96
`INFO_STRING_DISK_TEMPLATE` (OVF attribute), 96
`INFO_STRING_FILE_TEMPLATE` (OVF attribute), 97
`input_file` (VMDescription attribute), 45
`install_file()` (COT.helpers.helper.Helper class method), 82
`install_file()` (in module COT.helpers.api), 81
`install_helper()` (COTInstallHelpers method), 63
`install_helper()` (FatDisk method), 83
`install_helper()` (Helper method), 82
`install_helper()` (MkIsoFS method), 84
`install_helper()` (OVFTool method), 84
`install_helper()` (QEMUImg method), 86
`install_helper()` (VmdkTool method), 87
`install_manpages()` (in module COT.install_helpers), 63
`InvalidInputError`, 65
`IOSv` (class in COT.platforms), 71
`IOSXRv` (class in COT.platforms), 71
`IOSXRvLC` (class in COT.platforms), 72
`IOSXRvRP` (class in COT.platforms), 71
`item_match()` (OVFHardware method), 100
`item_tag_for_namespace()` (OVFNameHelper1 method), 104

L

`labels` (COTEditProperties attribute), 61
`list_union()` (in module COT.ovf.item), 104
`LITERAL_CLI_STRING` (CSR1000V attribute), 70
`LITERAL_CLI_STRING` (GenericPlatform attribute), 70
`LITERAL_CLI_STRING` (IOSv attribute), 71
`LITERAL_CLI_STRING` (IOSXRv attribute), 71
`LITERAL_CLI_STRING` (NXOSv attribute), 73
`locator` (COTDeployESXi attribute), 56

M

`mac_address()` (in module COT.data_validation), 67
`mac_addresses_list` (COTEditHardware attribute), 58
`main()` (CLI method), 77
`main()` (in module COT.cli), 78
`make_install_dir()` (COT.helpers.helper.Helper class method), 83
`manpages_helper()` (COTInstallHelpers method), 63
`match_or_die()` (in module COT.data_validation), 67
`memory` (COTEditHardware attribute), 58
`MEMORY_REGEX` (COTEditHardware attribute), 57
`MkIsoFS` (class in COT.helpers.mkisofs), 84

N

`name` (Helper attribute), 83
`name` (MkIsoFS attribute), 84
`name_helper()` (in module COT.ovf.name_helper), 105
`namespace_for_item_tag()` (OVFNameHelper1 method), 104
`namespace_for_resource_type()` (OVFNameHelper1 method), 104
`natural_sort()` (in module COT.data_validation), 67
`network_descriptions` (COTEditHardware attribute), 58
`network_descriptions` (OVF attribute), 97
`network_descriptions` (VMDescription attribute), 45
`network_map` (COTDeploy attribute), 54
`networks` (OVF attribute), 97
`networks` (VMDescription attribute), 45
`new_item()` (OVFHardware method), 100
`nic_names` (COTEditHardware attribute), 58
`nic_networks` (COTEditHardware attribute), 58
`nic_type` (COTEditHardware attribute), 58
`nic_types` (COTEditHardware attribute), 58
`NIC_TYPES` (in module COT.data_validation), 68
`nics` (COTEditHardware attribute), 58
`no_whitespace()` (in module COT.data_validation), 67
`non_negative_int()` (in module COT.data_validation), 67
`NSM` (OVFNameHelper0 attribute), 104
`NSM` (OVFNameHelper1 attribute), 105
`NSM` (OVFNameHelper2 attribute), 105
`NXOSv` (class in COT.platforms), 72

O

`open()` (FileInTAR method), 68

open() (FileOnDisk method), 69
 output (COTSubmodule attribute), 50
 output_file (OVF attribute), 97
 output_file (VMDescription attribute), 45
 OVF (class in COT.ovf.ovf), 88
 ovf_version (OVF attribute), 97
 OVHardware (class in COT.ovf.hardware), 99
 OVHardwareDataError, 99
 OVItem (class in COT.ovf.item), 102
 OVItemDataError, 102
 OVNameHelper0 (class in COT.ovf.name_helper), 104
 OVNameHelper1 (class in COT.ovf.name_helper), 104
 OVNameHelper2 (class in COT.ovf.name_helper), 105
 OVFTool (class in COT.helpers.ovftool), 84
 ovftool_args (COTDeployESXi attribute), 56

P

package (COTReadOnlySubmodule attribute), 49
 package (COTSubmodule attribute), 50
 package_list (COTInfo attribute), 62
 PACKAGE_MANAGERS (Helper attribute), 83
 parse_args() (CLI method), 77
 password (COTDeploy attribute), 54
 path (Helper attribute), 83
 path (MkIsoFS attribute), 84
 platform (OVF attribute), 97
 platform (VMDescription attribute), 45
 PLATFORM_NAME (CSR1000V attribute), 71
 PLATFORM_NAME (GenericPlatform attribute), 70
 PLATFORM_NAME (IOSv attribute), 71
 PLATFORM_NAME (IOSXRv attribute), 71
 PLATFORM_NAME (IOSXRvLC attribute), 72
 PLATFORM_NAME (IOSXRvRP attribute), 72
 PLATFORM_NAME (NXOSv attribute), 73
 port_install() (COT.helpers.helper.Helper class method), 83
 positive_int() (in module COT.data_validation), 67
 power_on (COTDeploy attribute), 54
 product (COTEditProduct attribute), 60
 product (OVF attribute), 97
 product_class (COTEditProduct attribute), 60
 product_class (OVF attribute), 97
 product_class (VMDescription attribute), 45
 product_url (COTEditProduct attribute), 60
 product_url (OVF attribute), 97
 profile_info_list() (OVF method), 93
 profile_info_string() (OVF method), 93
 profile_info_string() (VMDescription method), 41
 PROFILE_INFO_TEMPLATE (OVF attribute), 97
 profiles (COTEditHardware attribute), 58
 properties (COTEditProperties attribute), 61
 properties (OVFItem attribute), 104
 property_names (OVFItem attribute), 104
 property_profiles() (OVFItem method), 103

property_values() (OVFItem method), 103
 PyVmomiVMReconfigSpec (class in COT.deploy_esxi), 56

Q

QEMUImg (class in COT.helpers.qemu_img), 85

R

ready_to_run() (COTAddDisk method), 51
 ready_to_run() (COTAddFile method), 53
 ready_to_run() (COTDeploy method), 54
 ready_to_run() (COTDeployESXi method), 56
 ready_to_run() (COTEditHardware method), 57
 ready_to_run() (COTEditProduct method), 60
 ready_to_run() (COTEditProperties method), 60
 ready_to_run() (COTGenericSubmodule method), 49
 ready_to_run() (COTInfo method), 62
 ready_to_run() (COTInjectConfig method), 62
 ready_to_run() (COTReadOnlySubmodule method), 49
 ready_to_run() (COTRemoveFile method), 63
 ready_to_run() (COTSubmodule method), 50
 register_namespace() (in module COT.xml_file), 48
 remove_file() (OVF method), 93
 remove_file() (VMDescription method), 42
 remove_profile() (OVFItem method), 103
 RES_MAP (OVNameHelper1 attribute), 105
 run() (CLI method), 77
 run() (COTAddDisk method), 51
 run() (COTAddFile method), 53
 run() (COTDeploy method), 54
 run() (COTDeployESXi method), 56
 run() (COTEditHardware method), 57
 run() (COTEditProduct method), 60
 run() (COTEditProperties method), 61
 run() (COTGenericSubmodule method), 49
 run() (COTHelp method), 61
 run() (COTInfo method), 62
 run() (COTInjectConfig method), 62
 run() (COTInstallHelpers method), 63
 run() (COTRemoveFile method), 63
 run() (COTSubmodule method), 50

S

scsi_subtype (COTEditHardware attribute), 58
 scsi_subtypes (COTEditHardware attribute), 58
 search_for_elements() (in module COT.add_disk), 52
 search_from_controller() (OVF method), 93
 search_from_controller() (VMDescription method), 42
 search_from_file_id() (OVF method), 94
 search_from_file_id() (VMDescription method), 42
 search_from_filename() (OVF method), 94
 search_from_filename() (VMDescription method), 42
 secondary_config_file (COTInjectConfig attribute), 62

SECONDARY_CONFIG_TEXT_FILE (GenericPlatform attribute), 70
SECONDARY_CONFIG_TEXT_FILE (IOSXRv attribute), 71
SECONDARY_CONFIG_TEXT_FILE (IOSXRvLC attribute), 72
serial_connection (COTDeploy attribute), 54
serial_connection (COTDeployESXi attribute), 56
serial_connectivity (COTEditHardware attribute), 58
serial_ports (COTEditHardware attribute), 58
SerialConnection (class in COT.deploy), 54
server (COTDeployESXi attribute), 56
set_capacity_of_disk() (OVF method), 94
set_cpu_count() (OVF method), 94
set_cpu_count() (VMDescription method), 42
set_ide_subtype() (VMDescription method), 42
set_ide_subtypes() (OVF method), 94
set_ide_subtypes() (VMDescription method), 42
set_instance_attributes() (CLI static method), 77
set_item_count_per_profile() (OVFHardware method), 100
set_item_values_per_profile() (OVFHardware method), 101
set_memory() (OVF method), 94
set_memory() (VMDescription method), 43
set_nic_count() (OVF method), 94
set_nic_count() (VMDescription method), 43
set_nic_mac_addresses() (OVF method), 95
set_nic_mac_addresses() (VMDescription method), 43
set_nic_names() (OVF method), 95
set_nic_names() (VMDescription method), 43
set_nic_networks() (OVF method), 95
set_nic_networks() (VMDescription method), 43
set_nic_type() (VMDescription method), 44
set_nic_types() (OVF method), 95
set_nic_types() (VMDescription method), 44
set_or_make_child() (COT.xml_file.XML class method), 47
set_property() (OVFItem method), 103
set_property_value() (OVF method), 95
set_property_value() (VMDescription method), 44
set_scsi_subtype() (VMDescription method), 44
set_scsi_subtypes() (OVF method), 96
set_scsi_subtypes() (VMDescription method), 44
set_serial_connectivity() (OVF method), 96
set_serial_connectivity() (VMDescription method), 44
set_serial_count() (OVF method), 96
set_serial_count() (VMDescription method), 45
set_value_for_all_items() (OVFHardware method), 101
set_verbosity() (CLI method), 78
should_not_be_installed_but_is() (Helper method), 83
size() (FileInTAR method), 68
size() (FileOnDisk method), 69
SmarterConnection (class in COT.deploy_esxi), 56
strip_ns() (COT.xml_file.XML class method), 48
subcommand (COTHelp attribute), 61
subparsers (COTDeploy attribute), 54
subtype (COTAddDisk attribute), 51
SUPPORTED_NIC_TYPES (CSR1000V attribute), 71
SUPPORTED_NIC_TYPES (GenericPlatform attribute), 70
SUPPORTED_NIC_TYPES (IOSv attribute), 71
SUPPORTED_NIC_TYPES (IOSXRv attribute), 71
SUPPORTED_NIC_TYPES (NXOSv attribute), 73
system_types (OVF attribute), 97
system_types (VMDescription attribute), 45

T

tar() (OVF method), 96
terminal_width (CLI attribute), 78
terminal_width (UI attribute), 74
to_string() (in module COT.data_validation), 67
transports (COTEditProperties attribute), 61
truth_value() (in module COT.data_validation), 68

U

UI (class in COT.ui_shared), 73
UI (COTGenericSubmodule attribute), 49
untar() (OVF method), 96
unwrap_connection_error() (SmarterConnection static method), 56
update_existing_item_count_per_profile() (OVFHardware method), 101
update_xml() (OVFHardware method), 101
user_configurable (COTEditProperties attribute), 61
username (COTDeploy attribute), 54

V

validate() (OVFItem method), 103
validate_and_update_file_references() (OVF method), 96
validate_and_update_networks() (OVF method), 96
validate_controller_address() (in module COT.add_disk), 52
validate_cpu_count() (COT.platforms.CSR1000V class method), 70
validate_cpu_count() (COT.platforms.GenericPlatform class method), 69
validate_cpu_count() (COT.platforms.IOSv class method), 71
validate_cpu_count() (COT.platforms.IOSXRv class method), 71
validate_cpu_count() (COT.platforms.NXOSv class method), 72
validate_elements() (in module COT.add_disk), 53
validate_hardware() (OVF method), 96
validate_hardware() (VMDescription method), 45
validate_int() (in module COT.data_validation), 68

[validate_kind\(\)](#) (COT.deploy.SerialConnection class method), 55
[validate_memory_amount\(\)](#) (COT.platforms.CSR1000V class method), 70
[validate_memory_amount\(\)](#) (COT.platforms.GenericPlatform class method), 70
[validate_memory_amount\(\)](#) (COT.platforms.IOSv class method), 71
[validate_memory_amount\(\)](#) (COT.platforms.IOSXRv class method), 71
[validate_memory_amount\(\)](#) (COT.platforms.NXOSv class method), 72
[validate_nic_count\(\)](#) (COT.platforms.CSR1000V class method), 70
[validate_nic_count\(\)](#) (COT.platforms.GenericPlatform class method), 70
[validate_nic_count\(\)](#) (COT.platforms.IOSv class method), 71
[validate_nic_count\(\)](#) (COT.platforms.IOSXRv class method), 71
[validate_nic_count\(\)](#) (COT.platforms.IOSXRvRP class method), 72
[validate_nic_type\(\)](#) (COT.platforms.GenericPlatform class method), 70
[validate_nic_types\(\)](#) (COT.platforms.GenericPlatform class method), 70
[validate_options\(\)](#) (COT.deploy.SerialConnection class method), 55
[validate_ovf\(\)](#) (OVFTool method), 85
[validate_serial_count\(\)](#) (COT.platforms.CSR1000V class method), 70
[validate_serial_count\(\)](#) (COT.platforms.GenericPlatform class method), 70
[validate_serial_count\(\)](#) (COT.platforms.IOSv class method), 71
[validate_serial_count\(\)](#) (COT.platforms.IOSXRv class method), 71
[validate_serial_count\(\)](#) (COT.platforms.IOSXRvLC class method), 72
[validate_serial_count\(\)](#) (COT.platforms.NXOSv class method), 73
[validate_value\(\)](#) (COT.deploy.SerialConnection class method), 55
[value_add_wildcards\(\)](#) (OVFItem method), 104
[value_replace_wildcards\(\)](#) (OVFItem method), 104
[ValueMismatchError](#), 65
[ValueTooHighError](#), 65
[ValueTooLowError](#), 65
[ValueUnsupportedError](#), 65
[vendor](#) (COTEditProduct attribute), 60
[vendor](#) (OVF attribute), 97
[vendor_url](#) (COTEditProduct attribute), 60
[vendor_url](#) (OVF attribute), 98
[verbosity](#) (COTInfo attribute), 62
[verbosity_options](#) (VMDescription attribute), 46
[verify_manpages\(\)](#) (in module COT.install_helpers), 63
[version](#) (COTEditProduct attribute), 60
[version](#) (Helper attribute), 83
[version_long](#) (OVF attribute), 98
[version_long](#) (VMDescription attribute), 46
[version_short](#) (OVF attribute), 98
[version_short](#) (VMDescription attribute), 46
[virtual_system_type](#) (COTEditHardware attribute), 58
[vm](#) (COTGenericSubmodule attribute), 49
[vm_name](#) (COTDeploy attribute), 54
[VMContextManager](#) (class in COT.vm_context_manager), 46
[VMDescription](#) (class in COT.vm_description), 37
[VmdkTool](#) (class in COT.helpers.vmdktool), 86
[VMFactory](#) (class in COT.vm_factory), 46
[VMInitError](#), 37

W

[write\(\)](#) (OVF method), 96
[write\(\)](#) (VMDescription method), 45
[write_xml\(\)](#) (XML method), 48

X

[XML](#) (class in COT.xml_file), 46
[xml_reindent\(\)](#) (XML method), 48

Y

[yum_install\(\)](#) (COT.helpers.helper.Helper class method), 83